

ADOBE® ULTRA® CS3

USER GUIDE

UI

© 2007 Adobe Systems Incorporated. All rights reserved.

Adobe® Ultra® CS3 User Guide for Windows®

If this guide is distributed with software that includes an end user agreement, this guide, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by any such license, no part of this guide may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated. Please note that the content in this guide is protected under copyright law even if it is not distributed with software that includes an end user license agreement.

The content of this guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Please remember that existing artwork or images that you may want to include in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from the copyright owner.

Any references to company names in sample templates are for demonstration purposes only and are not intended to refer to any actual organization.

Adobe, the Adobe logo, Adobe Premiere Pro, After Effects, Creative Suite, and Ultra are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Windows and Windows Vista are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Apple is a trademark of Apple Inc., registered in the United States and other countries. All other trademarks are the property of their respective owners.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA.

Notice to U.S. Government End Users. The Software and Documentation are “Commercial Items,” as that term is defined at 48 C.F.R. §2.101, consisting of “Commercial Computer Software” and “Commercial Computer Software Documentation,” as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §§227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States. Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

Contents

Chapter 1: Getting started	9
Installation	9
Installing the software	9
Choosing PAL or NTSC video format	9
ReadMe	10
Resources	10
Adobe Help resources	10
In-product and LiveDocs Help	10
PDF documentation	10
Printed documentation	11
Adobe Video Workshop	11
Community of presenters	11
Tutorials and source files	11
Using Adobe Video Workshop	12
Extras	12
Adobe Design Center	12
Adobe Developer Center	12
Customer support	13
Downloads	13
Adobe Labs	13
User communities	14
Essential features	14
 Chapter 2: Quick-start session	 17
Step-by-step workflow	17
Tutorial	18
 Chapter 3: Product overview	 21
Overview	21
Layers, inputs, and virtual sets	22
Active layer	24
Virtual sets	24
User interface	27
Input area and Input Preview Monitor	28
Layer thumbnails	29

Controls under the Input Preview Monitor	30
Tool buttons.....	30
Output Preview Monitor and previewing the output	31
Magnifying and repositioning the view in the monitors.....	33
Sliders	34
Grid controls.....	34
Timecode fields	34
Tabs	35
Keyer tab	35
Colors tab.....	38
Scene tab.....	40
Pan & Zoom tab	41
Input tab	42
Shadows tab	44
Output tab	45
Libraries	47
Application menus	48
File menu	48
View menu	49
Tools menu	50
Play menu.....	50
Help menu	51
Right-click context menus	51
Text and number boxes.....	51
Background and Input Clip thumbnails	51
Overlay thumbnail.....	52
Output Preview Monitor	52
Grid controls on the Scene, Input, and Pan & Zoom tabs.....	52
Items on the Virtual Sets, Backgrounds, Output Clips, Sessions, and Browse library tabs	52
Blank spot on one of the library tabs	53
Chapter 4: How to	55
Creating and managing Ultra sessions	55
Creating a session.....	55
Changing the default virtual set.....	55
Opening a session.....	55
Saving a session	56
Changing the default session's path	56
Saving a copy of a session	56
Working with a session on a different computer	56
Creating and assigning sources and virtual sets.....	57
Shooting video for Ultra.....	57
Live Preview	57
Setting up the camera	58

Controlling the lighting	58
Framing the subject	59
Optimizing the color screen backdrop	60
Reducing spill	61
Choosing the subject's wardrobe	61
Choosing the background or virtual set	62
Directing on a virtual set	62
Improving the quality of the source footage and facilitating recording.....	62
Assigning content to layers	63
Assigning source content to a layer	63
Matching the aspect ratio of a basic set's background with a session.....	65
Matching input clips and virtual sets	65
Adding overlay layers	66
Using a still image as the input clip	66
Supported input formats	67
Creating elements for a set or individual layers.....	68
Backgrounds	69
Overlays.....	70
Finished, composited scene.....	71
Advanced compositing tasks	72
Customizing a virtual set.....	73
Editing virtual set images.....	74
Moving virtual sets to an alternate location	75
Copying a single virtual set	75
Setting the key	76
Keying methods	76
Improving a background in the input clip	77
Set Key.....	78
Setting Key Points (Apply Points Method)	79
Single Key Point Method (One Color Pickup)	79
Multiple Key Points Method (Color Spread)	80
Keeping the shadow in an input clip	82
Cropping and spot masking the source clip.....	83
Cropping the edge of a frame.....	84
Painting a mask	84
Fine-tuning the Keyer settings	84
Viewing the key	85
Basic keying workflows	85
Saving and applying Keyer settings	88
Positioning layers and performing virtual camera moves	88
Differences between sets of Position controls	89
Adjusting the framing	90
Setting the size, position, and orientation of a layer plane	91

Changing the position and scale of a layer plane	92
Changing the orientation of a layer plane	93
Positioning insets in custom virtual sets	94
Moving and scaling an input within the layer plane: Input Offset controls	95
Moving and flipping the input vertically and horizontally	97
Rotating the input	97
Changing the scale of the input	98
Returning all grid settings to the defaults	99
Panning and zooming	99
Grid control	99
Adding and setting a pan and zoom point	101
Changing a pan and zoom point	102
Programming a continuous virtual move with multiple points ..	103
Programming multiple moves with pauses	103
Panning and zoom with different aspect ratios	103
Viewing a session without virtual camera moves	103
Achieving the correct timing for video clips	104
Trimming the In and Out Points in a video clip	104
Looping the clip	105
Specifying when a video clip begins playing in the session	105
Setting a pause point for a VirtualTrak effect	107
Adjusting the volume of a video clip	107
Fine-tuning the appearance of the video	107
Correcting colors	108
Making color corrections	109
Saving and applying color settings	110
Adding shadows and reflections	111
Enabling a shadow or reflection and making it the active one ..	111
Changing the position of a floor shadow	112
Changing the position of a wall shadow	116
Changing the appearance of a shadow or reflection	116
Saving and applying settings for a shadow or reflection	118
Defocusing a source	119
Saving the finished video	119
Outputting still images (Frame Sequence)	122
Outputting clips or stills with an alpha channel	122
Chapter 5: Troubleshooting and getting help	123
Updating software	123
Updating Ultra	123
Updating device drivers	123
Updating the Windows® operating system	124
Technical Support	124

Technical support web pages	124
Run the DirectX Diagnostic Tool	124
StatusLog.txt file	125
Symptoms and solutions	125
Index	127

If you haven't installed your new software, begin by reading some information on installation and other preliminaries. Before you begin working with your software, take a few moments to read an overview of the many resources available to you. You have access to instructional videos, plug-ins, templates, user communities, seminars, tutorials, RSS feeds, and much more for various Adobe products.

Installation

Installing the software

To review complete system requirements and recommendations for your Adobe® software, refer to the ReadMe file on the installation disc.

1. Quit any other Adobe applications running on your computer.
2. Insert the installation disc into your DVD drive, and follow the on-screen instructions.

NOTE

Be sure to first install and activate at least one component of Adobe Creative Suite 3 Production Premium or Master Collection. Adobe Ultra CS3 will only start on a computer on which Adobe Creative Suite 3 Production Premium or Master Collection has been activated.

Choosing PAL or NTSC video format

When you run the program for the first time, you select either NTSC or PAL as the default video format for new sessions. PAL and NTSC are two common standards for standard-definition broadcast television, each used in different regions of the world. The format that you choose affects the options that are available on the Output tab.

NOTE

To change the default video format for new sessions, select Tools > Application Settings.

ReadMe

The ReadMe file on the installation disc is also copied to the application folder during product installation. Open the file to read important information about the following topics:

- System requirements
- Installation (including uninstalling the software)
 - Troubleshooting
 - Customer support
 - Legal notices

Resources

Adobe Help resources

Documentation for your Adobe software is available in a variety of formats.

In-product and LiveDocs Help

In-product Help provides access to all documentation and instructional content available at the time that the software ships. You can access in-product Help by choosing Help > Adobe Ultra Help, or by pressing F1.

LiveDocs Help includes all the content from in-product Help, plus updates and links to additional instructional content available on the web. For some products, you can also add comments to the topics in LiveDocs Help. Find LiveDocs Help for your product in the Adobe Help Resource Center, at www.adobe.com/go/documentation.

Most versions of in-product and LiveDocs Help let you search across the Help systems of multiple products. Topics may also contain links to relevant content on the web or to topics in the Help of another product.

Think of Help, both in the product and on the web, as a hub for accessing additional content and communities of users. The most complete and up-to-date version of Help is always on the web.

PDF documentation

The contents of in-product Help are also available as a PDF that is optimized for printing. Other documents, such as installation guides and white papers, may also be provided as PDFs.

All PDF documentation is available through the Adobe Help Resource Center, at www.adobe.com/go/documentation. To see the PDF documentation included with your software, look in the Documents folder on the installation or content disc.

Printed documentation

Printed editions of the contents of in-product Help are available for purchase in the Adobe Store, at www.adobe.com/go/store. You can also find books published by Adobe publishing partners in the Adobe Store.

A printed workflow guide is included with all Adobe Creative Suite® 3 products, and some stand-alone Adobe products include a printed getting started guide.

Adobe Video Workshop

The Adobe Creative Suite 3 Video Workshop offers over 200 training videos covering a wide range of subjects for print, web, and video professionals.

You can use the Adobe Video Workshop to learn about any Creative Suite 3 product. Many videos show you how to use Adobe applications together.

When you start the Adobe Video Workshop, you choose the products you want to learn about and the subjects you want to view. You can see details about each video to focus and direct your learning.

Community of presenters

With this release, Adobe Systems invited the community of its users to share their expertise and insights. Adobe and Lynda.com present tutorials, tips, and tricks from leading designers and developers such as Joseph Lowery, Katrin Eismann, and Chris Georgenes. You can see and hear Adobe experts such as Lynn Grillo, Greg Rewis, and Russell Brown. In all, over 30 product experts share their knowledge.

Tutorials and source files

The Adobe Video Workshop includes training for novices and experienced users. You'll also find videos on new features and key techniques. Each video covers a single subject and typically runs about 3-5 minutes. Most videos come with an illustrated tutorial and source files, so you can print detailed steps and try the tutorial on your own.

Using Adobe Video Workshop

You can access Adobe Video Workshop using the DVD included with your Creative Suite 3 product. It's also available online at www.adobe.com/go/learn_videotutorials. Adobe will regularly add new videos to the online Video Workshop, so check in to see what's new.

Extras

You have access to a wide variety of resources that will help you make the most of your Adobe software. Some of these resources are installed on your computer during the setup process; additional helpful samples and documents are included on the installation or content disc. Other useful extras are also offered online by the Adobe Exchange community, at www.adobe.com/go/exchange.

During software installation, a number of resources are placed in the application folder on your computer: *[startup drive]\Program Files\Adobe\Adobe Ultra CS3*.

Ultra tutorials are available on the Adobe website at www.adobe.com/support/ultra. Click the Tutorials link to see the tutorials. The video files referred to in the tutorials are located in the folders in the Browse tab in Ultra.

Adobe Design Center

Adobe Design Center offers articles, inspiration, and instruction from industry experts, top designers, and Adobe publishing partners. New content is added monthly.

You can find hundreds of tutorials for design products and learn tips and techniques through videos, HTML tutorials, and sample book chapters.

New ideas are the heart of Think Tank, Dialog Box, and Gallery:

Think Tank articles consider how today's designers engage with technology and what their experiences mean for design, design tools, and society.

In Dialog Box, experts share new ideas in motion graphics and digital design.

The Gallery showcases how artists communicate design in motion.

Visit Adobe Design Center at www.adobe.com/designcenter.

Adobe Developer Center

Adobe Developer Center provides samples, tutorials, articles, and community resources for developers who build rich Internet applications, websites, content for mobile devices, and other projects using various Adobe products. The Developer Center also contains resources for developers who develop plug-ins for Adobe products.

In addition to sample code and tutorials, you'll find RSS feeds, online seminars, SDKs, scripting guides, and other technical resources.

Visit Adobe Developer Center at www.adobe.com/go/developer.

Customer support

Visit the Adobe Support website, at www.adobe.com/support, to find troubleshooting information for your product and to learn about free and paid technical support options. Follow the Training link for access to Adobe Press books, a variety of training resources, Adobe software certification programs, and more.

Downloads

Visit www.adobe.com/go/downloads to find free updates, tryouts, and other useful software. In addition, the Adobe Store (at www.adobe.com/go/store) provides access to thousands of plug-ins from third-party developers, helping you to automate tasks, customize workflows, create specialized professional effects, and more.

Adobe Labs

Adobe Labs gives you the opportunity to experience and evaluate new and emerging technologies and products from Adobe.

At Adobe Labs, you have access to resources such as these:

- Prerelease software and technologies
- Code samples and best practices to accelerate your learning
- Early versions of product and technical documentation
- Forums, wiki-based content, and other collaborative resources to help you interact with like-minded designers and developers

Adobe Labs fosters a collaborative software development process. In this environment, customers quickly become productive with new products and technologies. Adobe Labs is also a forum for early feedback, which the Adobe development teams use to create software that meets the needs and expectations of the community.

Visit Adobe Labs at www.adobe.com/go/labs.

User communities

User communities feature forums, blogs, and other avenues for users to share technologies, tools, and information. You can ask questions and find out how others are getting the most out of their software. User-to-user forums are available in English, French, German, and Japanese; blogs are posted in a wide range of languages.

To participate in forums or blogs, visit www.adobe.com/communities.

Essential features

Get superior keying results even from marginal sources.

Using Ultra Vector Keying™ technology, shots that used to be difficult to key—uneven lighting, wrinkled backgrounds, and frizzy hair—can be keyed in minutes. Ultra will even preserve the shadows of your subject and achieve complex keys with scene elements such as smoke, liquids, and transparent objects with minimal effort.

One-click keying

Ultra offers an extraordinary one-click keying feature for faster keying. Advanced controls, such as spill suppression, color restoration, and edge softening, can also be applied to fine-tune composites.

Sophisticated virtual sets made simple

Master Sets Libraries add high-end virtual set systems to Ultra. When used in conjunction with Ultra, these libraries can save you time and money by eliminating the need to rent specialized motion tracking cameras and 3D graphics workstations. Master Sets Libraries simulate conventional motion tracking by using the Ultra VirtualTrak™ system, which creates virtual camera moves from stationary camera shots and inserts video reflections into virtual scenes.

Broadcast quality using DV/HDV/HD

Ultra can use 16:9 widescreen and anamorphic widescreen sources, and it delivers excellent results from the reduced color bandwidth of DV video sources. Ultra also supports HD and HDV frame dimensions, including 1080i, 1080p, and 720p, with support for a variety of standard frame rates, including 24 fps.

High-speed GPU keying

Ultra allows users with newer graphics cards (GeForce 5700 and Radeon 9600 or better for standard-definition video; GeForce 6600 and Radeon 9800 or better for high-definition video) to dramatically increase rendering speeds by shifting processing to the graphics processing unit (GPU). Using GPU-based processing, Ultra can typically perform vector keying in near-real time at HD resolution (depending on system configuration and file types).

High-resolution keying with standard-definition cameras

Ultra offers a Plus-90 mode to allow standard-definition cameras to generate footage for use in high-definition scenes. Video frames are wider than they are tall, yet human subjects are taller than they are wide. To make the optimum use of the greatest number of pixels for shooting a subject, you can rotate your camera 90 degrees, using the longer axis of the frame as the new vertical axis. This provides an additional 33% of vertical resolution when using a video format with a 4:3 frame aspect ratio, and an additional 78% of vertical resolution when using a video format with a 16:9 frame aspect ratio.

Virtual shadows and reflections

You can use Ultra to insert virtual shadows into a scene. You can then adjust the shadow's size, perspective, and transparency. When using photographic or rendered backgrounds, you can insert virtual reflections displaying an inverted image of the keyed subject.

Create custom virtual environments

Add your own backgrounds, B sources, and semi-transparent foreground images to create your own virtual environments, complete with multiple-point pans and zooms. Large, high-definition custom background images can be explored with complex camera moves.

Support for high-resolution stills

Ultra offers support for high-resolution stills up to 4096x4096 pixels, allowing digital images to be used as high-definition input sources and backgrounds. With image support for BMP, JPG, PNG, TIFF, TGA, and PPM files, users can export high-resolution keyed stills for further editing or output to print or the web.

Extensive input and output

Video formats supported for input include AVI, QuickTime, MPEG, DV, and any format for which you have a compatible codec installed. The Invert Alpha option inverts alpha channels for compatibility with non-linear editing systems that use *film alpha* (interpret an alpha channel value of 0 as complete opacity). Output files can be uncompressed AVI, DV, or QuickTime. AVI and QuickTime files can be output using 24 bits per pixel or 32 bits per pixel (with an 8-bit alpha channel). Output files with alpha channels can be used directly by other programs, such as Adobe After Effects, for further compositing.

Step-by-step workflow

The following is an overview of the general workflow for creating a session, compositing, and exporting a movie with Adobe® Ultra® CS3.

NOTE

Steps 1, 4, and 10 are required.
Step 3 is required for the source input layer; other layers are optional.
Steps 5 through 9 may be optional, depending on the virtual set and sources that you use and what you're trying to accomplish in the scene.

Create a session with the appropriate frame aspect ratio: Choose File > New > New 4:3 Session or File > New > New 16:9 Session. (See [“Creating and managing Ultra sessions” on page 55.](#))

Assign a virtual set. (See [“Assigning content to layers” on page 63.](#))

3. Assign a source to each layer. (See [“Assigning content to layers” on page 63.](#))
4. Key the input clip. (See [“Setting the key” on page 76.](#))
5. Trim the video clips to the desired length, and specify whether each clip will loop. (See [“Cropping and spot masking the source clip” on page 83.](#))
6. Specify the scale, position, and orientation for each layer plane. Note that some layers in virtual sets may be locked, so you can't change them. It is best to set up the scale and position of the input clip and other layers at the beginning of the session. (See [“Setting the size, position, and orientation of a layer plane” on page 91.](#))
7. Position each input source on its layer plane. Use the Input Offset controls, which are at the center of the Input tab, to move and scale the active layer within its layer plane. (See [“Moving and scaling an input within the layer plane: Input Offset controls” on page 95.](#))
8. Program the virtual camera moves and panning and zooming effects. (See [“Panning and zooming” on page 99.](#))
9. Modify the video and audio as needed.

- Add virtual shadows or reflections. (See [“Adding shadows and reflections” on page 111.](#))
 - Correct color. (See [“Correcting colors” on page 108.](#))
 - Defocus the sources. (See [“Defocusing a source” on page 119.](#))
 - Adjust the audio volume of the clips. (See [“Adjusting the volume of a video clip” on page 107.](#))
10. Export the finished movie. (See [“Saving the finished video” on page 119.](#))

Tutorial

The following is a step-by-step example of a simple NTSC session that uses NTSC sample files included with Ultra.

1. Start Ultra.
2. Drag a background from the Animations folder on the Backgrounds tab onto the Background thumbnail.
3. On the Browse tab, double-click the NTSC Sample Clips folder to open it. Drag the Hands Apart (Wedding) clip onto the Input Clip thumbnail.

NOTE

The first frame in this clip shows only the greenscreen background. The method described in this tutorial only works for clips that have at least one frame that is a shot of only the background color screen.

4. Click the Set Key button on the Keyer tab. If the controls on the Keyer tab are disabled, click Input Clip thumbnail.
5. Drag the slider under the Output Preview Monitor to the time of 1 seconds (00:00:01.00), or enter this timecode in the timecode text box. A video frame showing two hands appears on the Output Preview Monitor.
6. On the Input tab, click the Set button to the right of the In Point text box. This makes it so that the first frame to appear in the movie is the frame at the time of 1 second in the input clip.
7. Move the Transparency slider on the Keyer tab to the left to 0.350, or type that value in the adjacent text box. The two hands become opaque.

NOTE

The Hands Apart clip has a well-lit, even background that can be keyed out well with only this one adjustment. Some backgrounds require more manual fine-tuning to achieve a clean, convincing key. For more information, see [“Fine-tuning the Keyer settings” on page 84.](#)

8. (Optional) To view the resulting composited video, click the Play button under the Output Preview Monitor.
9. In the Output tab, choose DirectShow (.avi) from the Format menu, and choose MJPEG Compressor.
10. Make sure that the Folder that you are exporting to is set to \My Documents\Adobe Ultra CS3\My Output Clips.
11. (Optional) Change the name of the file in the File Name field.
12. Click Save Output. Ultra renders the movie.
13. To view the movie that you've just created, right-click the thumbnail image for the new video file on the Output Clips tab, and choose Play. If you do not see your video in the Output Clips tab, click the Home button in the navigation bar.

Overview

Adobe® Ultra® CS3 is a stand-alone keying and compositing application designed to use many kinds of video sources. The keying process starts with loading a virtual set, video clips, or both. You then calibrate the keyer, change any settings as needed, and record the output to a video file for use in an editing application, such as Adobe Premiere Pro or Adobe After Effects. Ultra is compatible with many standard video formats and has been fine-tuned to provide high-quality output and smooth performance, even with DV clips. You can immediately see any changes to the keyer quality settings.

Ultra exceeds other tools in many ways. One of the most noteworthy and powerful ways is that Adobe offers a wide range of virtual sets that provide background and, in many cases, foreground elements for video clips. Virtual sets come in collections known as *master sets* that have a variety of camera angles for the same virtual 3D environment. Available in packages known as *Master Sets Libraries*, most master sets have at least one set with virtual camera motions that use the Adobe VirtualTrak camera tracking system. You can use your own videos, digital images, and graphics as backgrounds, foregrounds, and insets for composited movies created in Ultra.

Ultra contains advanced features and innovations that separate it from conventional chroma keyers (color keyers).

With Live Preview, you can adjust the lighting, camera placement, angle, and zoom to fit the set that you are using before you shoot the source footage.


Dynamic controls let you adjust the size, position, and orientation of the source video and other layers in the virtual set.

Up to four independent overlays let you easily customize virtual sets and add dimension to composited movies.

The pan and zoom features let you add virtual camera moves and zooms to scenes.

The GPU Boost feature substantially speeds up keying and compositing.


Layers, inputs, and virtual sets




A) Composited output B) Overlay C) Input clip (subject) D) Background E) Source B (inset)


Input name	Definition
------------	------------

Virtual set	<p>All Ultra sessions have a virtual set. A virtual set can be as simple as one of the Simple Keyed virtual sets—which are empty sets—or as complex as one of the sets in the Master Sets Libraries. Some virtual sets have transparent (alpha) regions for insets, with a predefined scale, position, and orientation. Some virtual sets also have foreground elements such as doors, desks, and podiums. To customize the colors or otherwise manipulate the layers of a virtual set, you must switch from the standard User-Defined Inputs mode to the Pre-Defined Inputs mode (View > Displayed Inputs > Pre-Defined). For more information about virtual sets, see “Virtual sets” on page 24.</p> <p>Ultra comes with a few included virtual sets, including one of the Master Sets Libraries, MSL1. Adobe sells additional collections of virtual sets as Master Sets Libraries. You can also create your own custom virtual sets.</p>
-------------	--

Input name	Definition
Background	<p>This is typically the main layer behind the subject, filling the entire frame. The background can have one or more alpha regions that show through to insets behind it.</p> <p>You usually set backgrounds only in sessions that use one of the basic virtual sets. In most cases, advanced virtual sets define their own backgrounds; virtual sets that show the input clip as an inset are the only ones that let you define a background. The virtual set defines the foreground around the inset, but the Background assignment defines the background for the input clip. For example, in the Museum Painting Center (MSL1) virtual set, the  icon represents the input clip. Some shots in the Master Sets Libraries are tightly framed shots of one of the virtual monitors in the set. In these shots, the input clip and the background are both scaled inside the monitor frame, with the background behind the input clip.</p> <p>By adjusting the scale, position, and orientation of the Background layer, you can essentially turn it into a midground layer that sits behind the subject, but does not fill the frame. In this case, you typically use an inset (Source B) to fill the frame. For an example of this type of a session, see Ultra Tutorial #7 on the Ultra support web page, www.adobe.com/support/ultra.</p>
Input Clip or Live Preview	<p>This is the main video source shot against a greenscreen or bluescreen, which you key and composite with the other layers. It sits behind the overlays but in front of all of the other layers, and is sometimes referred to as the <i>subject</i>. When the subject is a person, the term <i>talent</i> is sometimes used.</p>
Source B, Source C, and so on	<p>The layers identified as Source B, Source C, and so on (also called insets) sit behind the background. In most cases, they appear as insets that show through transparent regions in the background. The number of insets is defined by the virtual set. Each inset is a separate layer.</p>
Overlay 1, Overlay 2, Overlay 3, and Overlay 4	<p>Overlays sit in front of everything else in the composited scene. They almost always have an alpha channel that defines transparent and semi-transparent areas so that you can see through to the underlying layers, but you can achieve the same result in some situations by scaling the image down to an appropriate size. You can add up to four overlays, each of which is a separate layer. For more information, see “Adding overlay layers” on page 66.</p> <p>The following are some examples:</p> <ul style="list-style-type: none"> • Props that add dimension to the scene • Doors, pillars, and so on, from behind which the subject enters • Titles, lower thirds, and captions • Watermarks and semitransparent logos, such as those that often appear in a lower corner of the frame in a television program

Active layer

To manipulate a layer by using any of the tabs, the layer must be the active layer. To make a layer the active layer, either click its thumbnail or select it from the list below the Input Preview Monitor. The active layer is displayed in the Input Preview Monitor, and the light next to the layer's thumbnail image is bright (lit) green .



A) Active layer B) Source for active layer C) Assign new source to active layer D) List for choosing active layer

The Overlay option appears in the list below the Input Preview Monitor only if an overlay source is assigned. From this list, you can also select Live Preview, which is intended only for setting up a shot and confirming that it will key well. For more information, see [“Shooting video for Ultra” on page 57](#).

The Browse button provides one of several ways to assign a source to the active layer. For more information, see [“Assigning source content to a layer” on page 63](#). To determine which folder a source came from, click the Browse button to open a dialog box that shows the source's current location.

To make a particular inset or overlay the active layer when two or more of them are in a session, click the field above the thumbnail, and select the layer from the list. If you use the list below the Input Preview Monitor to select Inset or Overlay, the currently selected inset or overlay layer becomes the active layer.

Assigning a source to a layer by dragging the source to the layer thumbnail does not make that layer the active layer.

Virtual sets

Virtual sets range from simple to complex. Virtual sets in the Basic folder are the simplest; they are essentially blank sets for which you assign the background and up to four overlays and four inset sources. Only the insets in these virtual sets have a predefined size and position, and you'll probably want to customize those settings.

The “Corner Office Monitor to Talent - Pause at Beginning (Trak) Sitting” virtual set is one of the most complex sets in all of the Master Sets Libraries. This virtual set starts with a pause point on an inset, and then performs a virtual camera move to the subject, which is composited between two predefined layers: a desk in front and a wall of windows behind looking out on a cityscape.

A Master Set is a collection of virtual sets with a unified appearance and layout, each of which is essentially a different perspective on the same 3D environment. A virtual set file from one of the Master Sets Libraries (MSLs) defines a group of inputs and their positions, some of which are predefined and others of which you assign. Designations for insets are consistent throughout a Master Set. For example, Source D in one set is in the same relative position in any other set from the same Master Set that uses a Source D. That’s why the insets in some sets do not start at Source B.

The virtual sets provided with Ultra have a file extension of .mfx.

Each virtual set has a native frame aspect ratio. In most cases, you should match the frame aspect ratio of the virtual set to the frame aspect ratio of the session as set on the Output tab. However, Ultra lets you mix them if that suits your purposes. You will find 16:9 sets in the Basic folder on the Virtual Sets tab.

NOTE

With the exception of those sets labeled 16x9, Ultra Master Sets use a 4:3 frame aspect ratio. For instructions on converting this aspect ratio for a widescreen session, see Tutorial #15 “Using 4:3 sets in a 16:9 project” on the Ultra support website, www.adobe.com/support/ultra.

The name of a virtual set provided as a part of the Master Sets conveys the following information:

The first word or two indicates the master set to which the virtual set belongs.

This is usually followed by a description of the shot, typically the camera number or position. VirtualTrak sets are an exception, with names that typically describe the camera movement (for example, “Monitor to Stage” or “Dolly to Bookcase”).

NOTE

VirtualTrak is a proprietary feature included in some of the Ultra Master Sets Libraries. It provides virtual camera movement with a more realistic tracking motion than standard pan and zoom. This movement is not reproducible in custom-built virtual sets. Ultra virtual sets with “Trak” in the title have VirtualTrak functionality included.

This is followed by text that indicates if there’s a foreground element or if the VirtualTrak shot includes a pause point. For more information, see “[Setting a pause point for a VirtualTrak effect](#)” on page 107.

This is followed by the type of framing enclosed with parentheses: Tight, Medium, Wide, or Sitting. VirtualTrak effects are designated as “Trak”. For these, you should preview the tracking shot to determine its final framing. Virtual set names that have nothing in parentheses display the input clip (Source A) in an inset. In this case, any framing will work.



A) Tight: Designed for the subject to be framed from the chest up. B) Medium: Designed for the subject to be framed from the waist up. C) Wide: Designed for the subject to be standing, visible from head to foot, and possibly scaled down.

For instructions on assembling a set using your own graphics, see [“Creating elements for a set or individual layers” on page 68](#).


For more information, see the following sections:

[“Input area and Input Preview Monitor” on page 28](#)

[“Creating and assigning sources and virtual sets” on page 57](#)

User interface

This section provides an orientation to the controls and displays that you use in Adobe® Ultra®.



A) Input area B) Output area C) Controls area

The Ultra interface consists of the following main regions:

The input area in the upper left consists of the Input Preview Monitor and several controls that you can use to assign sources, select the active layer, preview the source content, and select tools for setting the key and panning and zooming. For more information, see [“Input area and Input Preview Monitor” on page 28](#).

The output area in the upper right contains the Output Preview Monitor, which displays the composited image, and controls for previewing the session. For more information, see [“Output Preview Monitor and previewing the output” on page 31](#).

The set of tabs along the bottom of the window serve many purposes. The six tabs on the left are for setting the key and making all of the necessary adjustments to the layers and sources. Near the center, the Output tab is for setting session properties and rendering the final composited movie. The tabs on the right provide access to libraries of virtual sets, sessions, and output movies and graphics. For more information, see [“Tabs” on page 35](#).

Input area and Input Preview Monitor



The input area consists of the following displays and controls related to the active layer and its assigned source:

- The layer thumbnails on the right are for choosing and showing which layer is the active layer.

- The Input Preview Monitor displays the source that's assigned to the active layer.

- The buttons below the Input Preview Monitor are for selecting the tools to change the view, set keying points, and paint a mask.

- The transport controls and slider are for previewing the active layer's source.

- The two fields below the slider are for selecting the active layer, assigning a source to it, and displaying the name of the layer and the source.

The Input Preview Monitor displays the source assigned to the active layer. This monitor shows the results of keyer and color correction settings and any masking if the input clip is selected. The settings for the size, position, and orientation for the layer plane or the source do not affect what is shown in the Input Preview Monitor.

You can view the Input Monitor with its original, unkeyed background or with the checkerboard alpha background. To switch between these display modes, choose View > Input Clip Preview Background, and then choose either Original Source or Alpha Grid.

A white rectangle in the Input Preview Monitor and Output Preview Monitor identifies the action-safe area. Content outside this area may not be visible if the output movie is viewed on a television. To show or hide the action-safe overlay, choose View > Safe Area Overlay or press Alt+S.

For more information, see [“Magnifying and repositioning the view in the monitors” on page 33](#).

Layer thumbnails

The small images to the right of the Input Preview Monitor are thumbnail images of the sources assigned to each layer. Clicking a thumbnail for a layer makes it the active layer. If there are multiple insets or overlay layers, you can select among them by using the list above the thumbnail. You can assign a source to a layer by dragging the source to the appropriate thumbnail image.

Thumbnail graphics: If no image icon is present, you will see the following symbols representing the available actions for the current set:



This layer requires a source for the current set, but none is currently assigned.




This layer is available for the current set, but no source is currently assigned.




No source can be assigned with the current set.

LED icons next to the thumbnails: The status of each layer is indicated by a light next to the layer's thumbnail image.

Bright (lit) green : Layer is the active layer.

Dark (unlit) green : Layer has content assigned, but is not the active layer.

Yellow : Layer is optional and has no source content assigned.

Red : Layer is not used in this session.


The Background and Input Clip thumbnails have right-click menus with which you can switch from a given source to a white, black, or checkerboard image and back again. For the Background thumbnail, these images can help you analyze the quality of the key for the input clip. For the Input Clip thumbnail itself, you may want to switch to one of these alternate sources to see the size, position, and orientation of the input clip's plane. However, assigning a new source in this fashion can cause you to lose a custom mask that you've painted.

For more information, see the following sections:

[“Layers, inputs, and virtual sets” on page 22](#)

[“Assigning content to layers” on page 63](#)

Controls under the Input Preview Monitor



A) Current time B) Transport controls C) Preview slider D) List for selecting which layer is the active layer E) Source for active layer F) Select new source for active layer

Current time: If the source assigned to the active layer is a video clip, then this field displays the current time in the video clip. This is an interactive field. You can type a timecode to jump to a specific time in the clip.

Transport controls: Standard controls for playing and navigating video clips.

Preview slider: This is the slider for manually previewing (*scrubbing*) video clips.


Active Layer list: Shows which layer is the active layer. To select a different layer to be the active layer, either select it from this list or click its thumbnail.

Current source: Shows the name of the file assigned as the source for the active layer. To change the source, type the name of another file in this field.

Browse button: Opens the standard Windows dialog box for selecting a new source. You can also use this button to check the path of the current source.

Tool buttons

Click the buttons along the bottom of the Input Preview Monitor to activate the following tools.

Key point (input clip only):  Clicking with this tool in the Input Preview Monitor sets a key point for either the One Color Pickup or Color Spread keying method. For more information, see [“Single Key Point Method \(One Color Pickup\)” on page 79](#) or [“Multiple Key Points Method \(Color Spread\)” on page 80](#). To delete the last key point that you set, press Ctrl+Z. To delete all of the key points that you set, click the Clear Points button on the Keyer tab.

Painting a mask (input clip only): For more information, see [“Painting a mask” on page 84](#).



Paint Mask: Drag with this tool in the Input Preview Monitor to create a transparent region. Zooming in decreases the size of the paint brush.



Mask Eraser: Drag with this tool in the Input Preview Monitor to erase a transparent region.

Pan and zoom: For more information, see [“Magnifying and repositioning the view in the monitors” on page 33](#).

Output Preview Monitor and previewing the output

The Output Preview Monitor displays a preview of the session as the output movie will appear if you save it with the current settings. If the input clip is keyed and all of the other sources are assigned, then the Output Preview Monitor displays the fully composited session. The frame aspect ratio of this monitor changes based on whether you select 4:3 or 16:9 on the Output tab.

A white rectangle in the Input Preview Monitor and Output Preview Monitor identifies the action-safe area. Content outside this area may not be visible if the output movie is viewed on a television. To show or hide the action-safe overlay, choose View > Safe Area Overlay or press Alt+S.



The Output Preview Monitor scales when you change the size of the Ultra application window. The Resolution setting on the Output tab controls the monitor's resolution, or image quality. If the Resolution setting is lower than the actual size of the Output Preview Monitor, then you may see some pixelation that will not be in the final output movie, because the monitor is enlarging the image beyond the resolution to which you will be exporting. If the Resolution setting is higher than the actual size of the Output Preview Monitor, then the image is scaled down to fit in the monitor.

Use the standard set of transport controls below the Output Preview Monitor to navigate and play the session. You can also drag the slider bar to preview the session. The timecode field in the lower-left corner displays the current position in the session. This is an interactive field, so you can enter a timecode to jump to a specific time.

To toggle playing the session in a continuous loop, choose Play > Loop Mode or press F9.

To preview the output in full-screen, press Alt+Enter. This shortcut also returns to the regular interface.


Panning and zooming in the Output Preview Monitor is one of several ways to control the scale of images or the framing of what's displayed. For more information, see [“Magnifying and repositioning the view in the monitors” on page 33](#).

If what you see in the Output Preview Monitor is not what you expect, and the Output Preview Monitor is set to full-frame view, then check the settings described in the following table.


Control	Tab	Description
Position In Scene	Scene	Controls the size and position of the layer plane. See “Changing the position and scale of a layer plane” on page 92.
Orientation In Scene	Scene	Controls the perspective of the layer plane in all three axes. See “Changing the orientation of a layer plane” on page 93.
Size in Scene	Scene	Controls the scale of the layer plane independent of the Z setting in the Position In Scene control. This option lets you scale the layer plane of the input clip in sets that lock the other Scene controls. See “Rescaling the input clip’s layer plane in a virtual set” on page 92.
Input Offset	Input	Controls the size and position of the image on the layer plane. See “Moving and scaling an input within the layer plane: Input Offset controls” on page 95.
Pan and Zoom	Pan and Zoom	Controls the region of the composited scene that will be shown for every frame of the exported output movie. See “Panning and zooming” on page 99.


Magnifying and repositioning the view in the monitors

You can pan and zoom within the Input Preview Monitor and Output Preview Monitor to move to and magnify any area of interest.

To zoom, position the pointer over the monitor and roll the mouse wheel; or drag vertically in the monitor with the Zoom tool .

To zoom in the Output Preview Monitor, use the Magnify Preview slider on the Keyer tab.

To pan around a zoomed image, drag in the monitor with the Move tool . With the Pan tool or Zoom tool selected, you can hold down the Ctrl key to temporarily activate the other tool.

To return a monitor to full-frame view, click the  button beneath the monitor.

NOTE

Reverting to the full-frame view when you’re finished examining part of the image with the Output Preview Monitor zoomed can help you avoid problems. These problems may result because you changed the size, position, and orientation of one or more layers, but forgot that the Output Preview Monitor was zoomed.


Sliders



Ultra provides many sliders. Dragging is the main method for adjusting a slider, but it isn't the only method. After you click a slider, you can also make fine adjustments by using the Right Arrow and Left Arrow keys. You can also enter values in the text boxes associated with some sliders.

Grid controls

Ultra provides several grid controls that you use by dragging vertically or horizontally, sometimes while you hold the Shift or Ctrl key. For fine control, hold down the Alt key while dragging; this refines the response by a factor of 10. As with sliders, you can enter a value in the numeric fields next to a grid control.



For more information about individual controls, see the following sections:

[“Setting the size, position, and orientation of a layer plane” on page 91](#)

[“Moving and scaling an input within the layer plane: Input Offset controls” on page 95](#)

[“Panning and zooming” on page 99](#)

Timecode fields

Trimming a video clip and specifying its start time, defining pause points, and programming pan and zoom moves all involve setting timepoints based on the time either in a given video clip or in the overall session. You can set these timepoints by dragging the preview slider to the desired frame and clicking the Set button for the appropriate control, or by typing the value in the text box. If you enter a timecode manually, do not click the Set button, because that overwrites the value you typed with the current timecode for the active layer.

Timecode in Ultra is relative to the beginning of the clip or the overall session. The timecode of the first frame of an untrimmed clip or scene is always 00:00:00.00.

In Point:	00:00:00.00	Set	Reset
Out Point:	00:00:11.04	Set	Reset

Tabs

This section describes the tabs that appear below the Input Preview Monitor and Output Preview Monitor.

Keyer tab

The Keyer tab consists of the following controls. The Matte Generation, Color Control, and Post-Processing controls are used to fine-tune the key. For more information, see [“Fine-tuning the Keyer settings” on page 84](#).

General controls

Enable: Turns the keyer on and off. The keyer is automatically enabled when you click the Set Key or Apply Points button. If you want to see the unkeyed input clip in the scene, you can deselect Enable to disable the keyer without losing any of the settings. For more information, see [“Setting the key” on page 76](#).

GPU Boost: When enabled, Ultra uses the graphics processing unit (GPU) for some keying functions, which reduces the load on the CPU and substantially accelerates previewing and exporting a keyed session. For more information, see [“Keying methods” on page 76](#).

Set Key: Clicking this button when nothing but the keying background is visible in the Input Preview Monitor calibrates the keyer using the Set Key method. If you set any points in the Input Preview Monitor, then this button changes to the Apply Points button. For more information, see [“Set Key” on page 78](#).

Apply Points: If you set any key points in the Input Preview Monitor, then clicking this button uses those points to set the key. For more information, see [“Setting Key Points \(Apply Points Method\)” on page 79](#).

Clear Points: This button deletes all key points that were set in the Input Preview Monitor, regardless of whether you’ve applied them yet. This does not clear the key so that the background becomes visible again; the only way to accomplish that after a clip is keyed is to disable the keyer by deselecting Enable. For more information, see [“Multiple Key Points Method \(Color Spread\)” on page 80](#).

Load: Loads saved settings, letting you transfer keyer settings from one session to another with clips using similar lighting.

Save: Saves the current settings, but not the key points. This lets you save your work so that you can further experiment, or transfer keyer settings from one session to another with clips using similar lighting.

Magnify Preview: This slider is one method for zooming on the Output Preview Monitor. For more information, see [“Magnifying and repositioning the view in the monitors” on page 33](#).

Matte Generation area

Start Threshold: Changes the range of colors that are accepted as transparent. You typically use this control if uneven lighting creates noise in the key.

Transparency: Controls the overall transparency of the source video. This control increases the range of transparency of the reference key color background, starting at the center (reference color) and moving outward into the surrounding hues. This information is displayed visually in the Alpha Curve graph.


Highlights: Controls the transparency in the lighter areas of the source video.

Shadows: Controls the transparency in the darker areas of the source clip.

Sensitivity: Controls the range of color accepted in proximity to the key color background. This control is useful for cleaning up the rough edges on dark foregrounds.

Alpha Curve: Increases and decreases the edge softness on the keyed source. This information is displayed visually in the Alpha Curve graph.

Alpha Curve graph: Graphically represents the Start Threshold, Transparency, and Alpha Curve settings. The following example explains how to read this graph.



A) Key B) Opaqueltransparent axis (opaque at the top) C) Subject D) Similar colors/distant colors axis (similar colors at left) E) Transparency: Sets range of transparency of reference key color F) Alpha Curve: Controls the softness of edges of keyed subject G) Start Threshold: Sets range of color made transparent H) All colors in this range are fully keyed out (transparent). I) Colors in this range are semi-transparent. 1: The color at this point is 25% opaque; 2: The color at this point is 75% opaque. J) All colors in this range are totally opaque (subject).

Color Control area

Start Level: Controls the starting range of the desaturation curve in the input clip. The effect of this setting on the Color Curve graph corresponds to that of the Start Threshold setting on the Alpha Curve graph.

Desaturation: When a foreground is photographed against a saturated key color background, some of the light bouncing off of the background falls on the foreground, causing the foreground to change to the hue of the replaced background. This is sometimes called *spill*. Desaturation compensates for spill by reducing the saturation of certain color ranges. This can simplify the correction of severe color problems in the input clip. The effect of this setting on the Color Curve graph corresponds to that of the Transparency setting on the Alpha Curve graph.

Spill Suppression: Decreases the level of spill color on the subject by adding the color opposite the key color to certain color ranges. This setting is used with the Desaturation setting.

Color Curve: Changes the dynamic of desaturation. You can use this control with spill suppression. The effect of this setting on the Color Curve graph corresponds to that of the Alpha Curve setting on the Alpha Curve display.

Post-Processing area

Shrink Matte: Shrinks the matte, which can help eliminate a troublesome halo around the subject. When pushed too far, this control can cause the edges of the subject to degrade and become transparent. Be careful if you change this setting.

Soften Matte: Blurs the edges of the matte, which can help smooth out jagged edges and other imperfections along the edges of the subject.

Sharpen Matte: Increases the focus at the edges of the matte. This control is essentially the opposite effect from the Soften Matte setting. Sharpen Matte works well with the Soften Matte setting to make the edges of the subject stronger and sharper.

Sharpen Range: Adjusts the direction of sharpening. This control works with the Sharpen Matte control.

TIP

If you want to experiment with the keyer settings to become familiar with what each control does, load RGB.jpg as the input clip. This file is included with Ultra and is located in the Colors folder on the Backgrounds tab. Set one key point on any color, click the Apply Points button, and then adjust the sliders to see what happens.

Colors tab

Enable: Enables and disables color processing. Disabling the color correction controls lets you quickly compare the original source without losing the settings. For the input clip, the Enable check box operates independently for the Pre-Processing and Post-Processing controls.

Reset button: Returns all of the settings to the application defaults, which are neutral.

Load button: Opens a dialog box where you can choose a color correction profile.

Save button: Opens a dialog box where you can save the current color correction settings as a profile that you can apply to other sessions.

Processing mode options:

Pre-Processing: For the input clip, adjusts colors before the input clip is keyed. You should limit Pre-processing adjustments to the input clip to changes that enhance the color of the background and allow better keying. You should perform all other color correction for this layer by using the Post-Processing controls. For more information, see [“Improving a background in the input clip” on page 77](#).

For layers other than the input clip, the distinction between pre-processing and post-processing is irrelevant because Ultra performs no processing on these layers that is comparable to the keying performed on the input clip. Therefore, all color correction is performed by using this set of controls.

NOTE

If pre-processing color corrections are made, you may need to readjust the keyer settings, because they will affect the material being keyed. It is best to perform pre-processing color correction prior to setting and adjusting a key.

Post-Processing: Applies to the input clip only. Changes made in this mode affect the color of the subject after keying. You can make these changes either to offset a pre-processing color correction that adversely changed the color of the subject or to balance the appearance of the subject with the appearance of the background and virtual set.

Brightness: Controls the intensity of luminance in the currently active source.

Contrast: Controls the degree of separation of light and dark shades in the currently active source.

Saturation: Controls the intensity of color in the current active source.

Hue: Controls the balance of colors used in the current active source.

All Channels: When selected, any changes that you make to the Level, Offset, and Gamma controls affect all of the color channels. When deselected, the options for Red, Green, and Blue are available.

Red, Green, and Blue: Selects which channel is active for adjustment through the Level, Offset, and Gamma controls. These options are available only when the All Channel check box is deselected.

Level: Adjusts the value of the current color channel on the 0-255 scale for all pixels that have a nonzero value in the current channel.

Offset: Adjusts the value of the current color channel on the 0-255 scale for all pixels, regardless of whether they originally had a value in the current channel.

Gamma: Differentially adjusts the value of the current color channel on the 0-255 scale, with the degree of change greatest if the original value was in the middle of the range and diminishing to nothing for values at the extremes.

Scene tab

Use the controls on the Scene tab to change the size, position, and orientation of some layers in the session. You may want to do this if, for example, you need to move the input clip so that it fits correctly in the scene. These controls are also used when you build your own set using the Basic sets. The Scene tab also contains a field for setting a pause point in a VirtualTrak scene.

Pause Point Settings area

This control group displays the preset start time for a pause in a VirtualTrack scene and lets you set the end time. These controls apply only to virtual sets from a Master Sets Library. All of the virtual sets that support this functionality have “with Pause” in their names.

Pause Begins At: Specifies a point in time that is specific to the current virtual set. Virtual sets with a pause point were created by the designer with the pause. You cannot edit this field, but it indicates where the pause begins.

Pause Ends At: Sets the duration of the pause. Enter the end time, which is equal to the desired pause duration plus the Pause Begins At time.

Size In Screen: Adjusts the size of the input clip while retaining its baseline position in the scene. The default size is 1.0.

Set: Sets the end point of the pause prebuilt into the virtual set using the current frame shown for the input clip. To use the Set button, drag the preview slider for the input clip to the time at which you want the pause to end.

Reset: Deletes the pause by setting the Pause Ends At time to the Pause Begins At time.

Position In Scene area

Grid control: This is an interactive control for positioning the layer plane. For more information, see [“Changing the position and scale of a layer plane” on page 92](#).

Numeric readouts: You can click in a field and type a value.

X: Moves the layer plane along the x (horizontal) axis.

Y: Moves the layer plane along the y (vertical) axis.

Z: Moves the video plane along the z (depth) axis, which changes the scale of the layer plane. The z axis is a third dimension added to the x and y grid. The z axis is perpendicular to both x and y axes. To change this setting, hold down the Shift key while dragging vertically.

Reset: Returns all of the values to the default settings. For virtual sets, the coordinates for the Input Source, and sometimes for other layers, are predefined. In these cases, the Reset button returns the values to the predefined coordinates, not to 0.00.

Orientation In Scene area

Grid control: This is an interactive control for setting the orientation of the layer plane. For more information, see [“Changing the orientation of a layer plane” on page 93](#).

Numeric readouts: You can click in a field and type the desired value.

X: Rotates the layer plane around the x axis.

Y: Rotates the layer plane around the y axis.

Z: Rotates the layer plane around the z axis.

Reset: Returns the values to the default settings. For virtual sets, the coordinates for the Input Source, and sometimes for other layers, are predefined. In these cases, the Reset button returns the values to the predefined coordinates, not to 0.00.

Pan & Zoom tab

Instructions for using the controls on the Pan & Zoom tab are provided in [“Panning and zooming” on page 99](#).

Enable: Turns panning and zooming on or off.

Pan & Zoom Points: Lists all of the points in order, and displays the time for each point. Selecting a point jumps to the associated frame, displays the programmed region of the image, and displays the x, y, and z coordinates for that position.

Add New Point: Inserts a point at the frame currently shown in the Output Preview Monitor.

Delete Current Point button: Deletes the selected point.

Time: This is an interactive field. If you add a point or select a point, the time for that point is displayed. If you enter a value in this field and press Enter, then the entered value becomes the time for the currently selected point.

Set To Preview Time: Changes the time for the currently selected point to the current time in the Output Preview Monitor.

Grid control: This is an interactive control that lets you use the mouse to set the framing for the pan and zoom point.

X: Sets and displays the horizontal position.

Y: Sets and displays the vertical position.

Z: Sets and displays the zoom setting.

Reset: Returns all of the settings to zero.

Input tab

Timing & Settings For Input Clip area

In Point and Out Point: These controls are used to trim the beginning and ending of the current video clip. Trimming a clip does not change the source clip in any way. For more information, see [“Trimming the In and Out Points in a video clip” on page 104](#).

Timecode: Indicates the current In Point or Out Point. This is an interactive field. You can click in this field, and then type a value. The default In Point is 0:00:00.00. The default Out Point is the last frame of the clip.

Set: Applies the current time in the clip, which is displayed in the lower-left of the Input Preview Monitor, to the In or Out Point. If you enter a value manually, do not click this button to apply the value, because the entered value will be overwritten with the current time for the clip.

Reset: Returns the timecode to the default (first frame or last frame).

Trimmed Duration: Specifies the length of the source video with the In and Out points applied.

Original Duration: Specifies the length of the source video untrimmed.

Offset Into Scene: Defines the time in the session when the current clip starts playing. This is typically required with VirtualTrak scenes where the input clip or an inset is not visible immediately. For more information, see [“Specifying when a video clip begins playing in the session” on page 105](#).

Timecode: Indicates how far into the session the clip’s start time is delayed. This is an interactive field.

Set: Applies the current time in the session, as displayed below the Output Preview Monitor, when the current clip starts playing.

Reset: Returns the Offset Into Scene timecode to zero.

Field Order: Ultra tries to set the field order automatically based on what it knows about the clip. If Ultra succeeds, then this can be left on Clip Default. If not, then you can use this list to specify which field should play first in interlaced clips or set it to Progressive for progressive clips. For more information, see [“Set the field order \(interlaced video clips only\)” on page 65](#).

Aspect: Ultra tries to determine the source’s native frame aspect ratio. If the image appears stretched or squeezed, you can correct it by manually selecting the aspect ratio from this list. For more information, see [“Setting the aspect ratio of the input source” on page 64](#).

Defocus: Makes the current video clip or still image a little blurry, as if it were out of focus. You may want to do this to simulate depth in the composited scene, as if you had shot the video clip with a camera lens that had a narrow depth of field. Some older video cards do not support this function. In this case, this slider does nothing. This control does not improve the focus of a source that was out of focus to begin with. For more information, see [“Defocusing a source” on page 119](#).

Loop Source: When enabled, causes the current video clip to loop for the duration of the scene. For more information, see [“Looping the clip” on page 105](#).

Invert Alpha: When enabled, Ultra reverses how it interprets the alpha channel data for the current source. This is for compatibility with applications that interpret the alpha channel as *film alpha*, in which a value of 0 indicates complete opacity. For more information, see [“Inputting sources that use film alpha, such as Avid \(Invert Alpha option\)” on page 65](#).

Volume: Controls the volume level of the audio in the selected source clip. The level that you set the audio to for each source is the level at which it will be recorded in the final output movie. You can also mute the audio for each clip by moving the Volume slider all the way to the left. For more information, see [“Adjusting the volume of a video clip” on page 107](#).

Input Offset area

This set of controls changes the size and position of the source on the layer plane. You should use these controls to move a source only if you cannot achieve the desired positioning by using controls on the Scene tab. For some video cards, you may need to use the Input Offset control with the Input Cropping control to avoid artifacts. For more information, see [“Moving and scaling an input within the layer plane: Input Offset controls” on page 95](#).

Grid control: This is an interactive control that lets you use the mouse to position the source.

Numeric readouts: You can click in a field and then type a value.

X: Indicates the position of the source in the horizontal axis.

Y: Indicates the position of the source in the vertical axis.

Angle: Indicates the rotational angle of the source on the layer plane. To change this setting, hold the Ctrl key while selecting the grid control and dragging vertically.

Scale: Indicates the size of the source. The range is 0.05 (1/20th) to 10 (10x). To change this setting, hold the Shift key while selecting and dragging vertically.

Reset: Returns the values to the default settings.

Check boxes: These controls let you make common adjustments with a single click.

Flip Vertical and Flip Horizontal: Flips the source vertically or horizontally. For more information, see [“Moving and flipping the input vertically and horizontally” on page 97](#).

Scale To Fit: When enabled, scales down the source so that the entire source image is visible in the layer plane. This assumes that all of the Input Offset values are zero. For more information, see [“Scaling an input source to fit the virtual set” on page 98](#).

Plus-90 (Portrait): Rotates the source 90° clockwise. For more information, see [“Turning the image 90° to display it in the portrait orientation” on page 97](#).

Input Cropping area

Use these controls to crop one or more edges of the source to mask out unwanted content in the frame. For more information, see [“Cropping and spot masking the source clip” on page 83](#).

Grid control: Drag any of the small green handles to interactively crop the source.

Numeric readouts: You can click in a field, and then type a value.

Reset: Returns the values in all of the cropping fields to zero.

Edge Softness: Applies a transparency gradient along all of the cropped edges and painted masks, blending these mattes with unmatted regions so that no harsh edges are evident.

TIP

You can also use the Mask Painter feature to create a matte for isolated spots rather than whole edges. For more information, see [“Painting a mask” on page 84](#).

Shadows tab

The Shadows tab provides controls for adding a virtual reflection and up to three virtual shadows to a scene. Although it's possible to have up to five shadows, they're not designed to all be on at once, because two shadows lie on the wall and three shadows fall on the floor. The controls in the Settings for Shadow Region change depending on which shadow or reflection is selected on the left.

For instructions on enabling and setting up shadows, see [“Adding shadows and reflections” on page 111](#).

Shadows & Reflections area

Reset: Returns all of the settings for the current shadow or reflection to the defaults.

Load: Opens a dialog box where you can choose a profile and apply it to the currently selected shadow or reflection.

Save: Opens a dialog box where you can save the settings for the current shadow or reflection as a profile.

Shadows & Reflections list: Select or deselect entries to enable or disable a shadow or reflection. To select a shadow or reflection so that the controls on the right are active, click anywhere on that row. The active shadow or reflection is highlighted in blue. You should not load the reflection settings for a shadow, or vice versa.

Appearance controls

Opacity: Controls the darkness and transparency of the shadow or reflection.

Falloff: Increasing this setting causes the shadow or reflection to fade starting at the far end.

Falloff Edge: Controls the distance over which the falloff occurs. When set to the far left (0.000), the shadow ends with a hard edge rather than fading over a gradient.

Blur: Increasing this setting causes the edges of the shadow to become blurred.

Floor shadow position controls

Flip Vertically check box: When enabled, displays the current shadow in front of the subject.

Baseline: Aligns the bottom of the current shadow with the feet of the subject.

Length: Controls the length of the shadow.

Angle: Controls the direction in which the shadow extends from the feet of the subject.

Spread: Increasing this setting causes the far end of the shadow to grow wider as if the light were close to the subject.

Wall shadow position controls

Grid control: This is an interactive control that lets you use the mouse to position a wall shadow.

Numeric readouts: You can click in a field, and then type a value.

X: Moves the shadow horizontally.

Y: Moves the shadow vertically.

Z: Shrinks and enlarges the shadow. To change this setting, Shift-drag vertically.

Output tab

All of the options and settings on this tab are described in [“Saving the finished video” on page 119](#), except for the 4:3 and 16:9 options, which are more relevant to creating sessions and setting their properties. For more information, see [“Creating and managing Ultra sessions” on page 55](#).

Output Settings area

Format: Specifies the exporter, which broadly determines the type of output.

DirectShow: AVI container

QuickTime: MOV container

Frame Sequence: A series of individual still image files, one per frame, rather than a single video clip.

Codec: Specifies the encoder used to encode and compress the output file. The options that are available in this list depend on the format that's selected. If you select DirectShow AVI, then the list of codecs depends on what's installed on the computer independently of Ultra.

Configure: Opens the configuration panel for the selected codec. This button is disabled for codecs that do not have any configuration options available.

24-bit / 32-bit Keyed Source: These options are available if you set the format and codec to QuickTime and Apple None or one of the other file formats that supports an alpha channel.

24-bit: Creates an output file with no alpha channel.

32-bit Keyed Source: Creates an output file with an alpha channel for use in another compositing application. The extra 8 bits per pixel is for the transparency information.

Invert Alpha: This option is available if you select 32-bit Keyed Source. When enabled, Ultra reverses how it encodes the alpha channel data. This is for compatibility with applications that interpret the alpha channel as *film alpha*, in which a value of 0 indicates complete opacity.

Type 1 and Type 2: These options are available if you set the format to DirectShow and set the codec to DV Video Encoder.

Type 1 DV: Saves a single stream containing both the video and audio.

Type 2 DV: The output consists of two streams: one stream for the audio and one stream for the video. This format is compatible with more applications than the Type 1 DV format.

Resolution: Specifies the dimensions of the frame for the output movie, in pixels. You cannot change the resolution for some codecs.

Frame Rate: Specifies the frame rate, in frames per second (fps), for the output movie.

Field Order: Specifies whether the output movie is progressive or interlaced. If the output movie is interlaced, this setting specifies which field is first.

Flicker Filter: If the output video has sharp lines of contrast and will be viewed on a television, reduces flickering or strobing along those lines.

File Information area

Folder: Displays the path where the output movie is saved.

Browse: Opens a dialog box where you can specify the path where the clip is saved.

File Name: This is an interactive field for entering and displaying the name by which the clip is saved.

Total Duration: This display-only field shows the length of the output video.

Estimated Size: This display-only field indicates approximately how large the video output file will be (in megabytes) if you save it with the current settings. If the currently selected codec uses a variable-bit-rate compression method, then nothing is displayed here.

Time Remaining: This display-only field shows an estimate of how much longer it will take to finish saving the movie.

Save Output: Starts rendering and saving the video file with the current output settings.

Progress: Displays a progress bar indicating how much of the session has been rendered and encoded.

Libraries

The five tabs on the right that contain the folder icons are for accessing Ultra sessions, various files that you use in the sessions, and the movies that you produce with Ultra.

Virtual Sets tab

This tab provides access to all of the virtual sets that are installed. Ultra CS3 includes the MSL1 Master Sets Library. If you have Ultra without additional Master Sets Libraries installed, then this tab contains the Basic folder, MSL1, and samples of virtual sets from the other Master Sets Libraries. For more information about virtual sets, see the following sections:

[“Virtual sets” on page 24](#)

[“Assigning content to layers” on page 63](#)

[“Customizing a virtual set” on page 73](#)

Backgrounds tab

The default path for this library is where the set of backgrounds included with Ultra are installed. Be sure to check out the Animations subfolder for the collection of dynamic 3D backgrounds that are provided standard with Ultra. For instructions on setting one of these images as a source, see [“Assigning content to layers” on page 63](#).

Output Clips tab

The path for this library is to the default location where the Ultra clips are stored when you save the output of a session. Changing the location where output movies are saved does not change this library's path. For more information, see [“Saving the finished video” on page 119](#).

Sessions tab

This library is for accessing Ultra sessions. Files in this library have an extension of .mks. The library's initial path is the default location where sessions are saved. For more information, see [“Creating and managing Ultra sessions” on page 55](#).

Browse tab

Whereas the other library tabs let you navigate to any folder on the system, this tab is specifically intended for this purpose. If you store raw input clips and background stills in one location, Adobe recommends that you set that folder as the home for the Browse tab.

Assigning a folder as a library's home

1. Click the desired library tab.
2. Navigate to the desired folder using the address bar.
3. Right-click a blank spot in the library. A context-sensitive menu is displayed.
4. Select Set Current Directory As Home for '<library>'.

Resetting a library tab to the default home

If you set a custom home for a library and want to revert to the default, click the library tab, and select Reset Default Home Directory For '<library>'.

Setting Ultra to remember the last folders that you were in

By default, each time you start Ultra and open a library, Ultra goes to the home folder for that library. If you prefer to have Ultra keep track of which folders you were in at the end of the last session, select Tools > Application Settings, and then select Remember Current Folders.

Application menus

This section describes the menus at the top of the Ultra application window.

File menu

New > New 4:3 Session (Ctrl+N) or New 16:9 Session (Ctrl+W): Creates a new Ultra session. For more information, see [“Creating a session” on page 55](#).

Open Session (Ctrl+O): Opens a previously saved Ultra session. For more information, see [“Opening a session” on page 55](#).

Save Session (Ctrl+S): Saves the current session. For more information, see [“Saving a session” on page 56](#).

Save Session As: Saves the current session under a different name. For more information, see [“Saving a copy of a session” on page 56](#).

Load Settings or Save Settings: Specifies which type of profile to apply to the current session or save from the current session.

Keyer (See [“Saving and applying Keyer settings” on page 88](#).)

Color (See [“Saving and applying color settings” on page 110](#).)

Shadow (See [“Saving and applying settings for a shadow or reflection” on page 118](#).)

Recent Virtual Sets: Loads a recently assigned virtual set.

Recent Inputs: Loads a recently assigned input source.

Recent Sessions: Loads a recently opened Ultra session.

View menu

Input Clip Preview Background: Sets the background for the input clip in the Input Preview Monitor to either the unkeyed original view (Alt+O) or the checkerboard alpha view (Alt+A). This option is used only if the input clip is the active layer, it's keyed, and the keyer is enabled. For more information, see [“Input area and Input Preview Monitor” on page 28](#).

Displayed Inputs: Specifies whether the layer thumbnails between the two monitors display the default user-defined sources (Alt+U) or the sources predefined by the current virtual set (Alt+P). To change the size, position, orientation, or color of any part of a virtual set, you must switch to the predefined view. For more information, see [“Customizing a virtual set” on page 73](#).

Safe Area Overlay: When this option is enabled, a white rectangle displays over the Input Preview Monitor and Output Preview Monitor to indicate the area of the image that is certain to be visible if the output movie is viewed on a television. Content outside this area may or may not be visible, depending on the particular television set. For more information, see [“Input area and Input Preview Monitor” on page 28](#).

Toggle Full-Screen (Alt+Enter): Toggles between full-screen video playback and the Ultra interface. For more information, see [“Output Preview Monitor and previewing the output” on page 31](#).

Tools menu

One-Click Key/Apply Points (Ctrl+K): Applies either the Set Key or Apply Points method to the input clip in the Input Preview Monitor. For more information, see [“Setting the key” on page 76](#).

Clear All Key Points (Ctrl+E): Clears all of the points from the input clip in the Input Preview Monitor. For more information, see [“Multiple Key Points Method \(Color Spread\)” on page 80](#).

Undo Last Key Point (Ctrl+Z): Clears the last key point entered. You can press Ctrl+Z repeatedly until you’ve cleared all of the key points entered.

Application Settings (F3): Opens the Application Settings dialog box, where you can set the following parameters:

Default Virtual Set field and Browse button: Specifies which virtual set is loaded for each new session. The Browse button opens a dialog box in which you can select a different set as the default. For more information, see [“Creating and managing Ultra sessions” on page 55](#).

Live Preview Setup controls: Configures the system for Live Preview, which is intended primarily for checking the quality of the lighting and camera settings prior to shooting content to be keyed in Ultra. For more information, see [“Live Preview” on page 57](#).

Device: Lists the compatible live video devices that are connected to the computer.

Underscan: Displays the percentage of underscan applied to the horizontal edges of the input source. This setting is involved in removing the black bars generated by some camcorders.

Resolution: Specifies the video resolution for the Live Preview. For slower computers, you may need to reduce this setting.

Remember Current Folder: When enabled, saves the path for each library tab each time you close Ultra and restores the paths the next time you start Ultra. When disabled, resets the libraries to the default paths each time you close Ultra. For more information, see [“Assigning a folder as a library’s home” on page 48](#).

Start Up In Last Session: When enabled, automatically opens the last session you were in when you start Ultra. When disabled, Ultra starts with a new, blank session. For more information, see [“Opening a session” on page 55](#).

Play menu

These commands control the playing of the session in the Output Preview Monitor.

Play/Pause (space bar): Plays and pauses.

Go To First Frame (F5): Displays the first frame.

Previous Frame (F6): Displays the previous frame.

Next Frame (F7): Displays the next frame.

Go To Last Frame (F8): Displays the last frame.

Loop Mode (F9): Plays from start to finish, continuously.

Help menu

Help (F1): Accesses the built-in Help document.

Online Support: Starts a web browser and opens the Ultra support page on the Adobe website.

FAQ: Starts a web browser and opens the Ultra FAQ web page.

Find More Sets Online: Starts a web browser and opens the Master Sets Library page on the Adobe website.

Updates: Checks for updates for Ultra.

About Adobe Ultra: Shows information about the currently installed version and your computer system.

Right-click context menus

This section describes the menu options that are available when you right-click on various areas in the Ultra application window.

Text and number boxes

Right-click in a text box for a standard text-editing menu with Undo, Cut, Copy, Paste, Delete, and Select All commands.

Background and Input Clip thumbnails

For more information, see [“Assigning content to layers” on page 63](#).

Assign Black, Assign White, or Assign Checkerboard: Assigns a black, white, or checkerboard image as the source for the selected layer.

Reassign Last Source: Assigns the previously assigned file as the source for the selected layer.

Unload Source: Removes the source assignment from the selected layer.

Overlay thumbnail

For more information, see [“Adding overlay layers” on page 66](#).

Add New Overlay: Adds a new entry so that you can load a new overlay graphic to the current session.

Remove Current Overlay: Deletes the overlay from the current session.

Output Preview Monitor

Reset All: Resets all of the zoom and positioning in the Output Preview Monitor to the defaults.

Reset Position: Resets all of the positioning in the Output Preview Monitor to the defaults.

Reset Magnification: Resets all of the zoom in the Output Preview Monitor to the defaults.

Grid controls on the Scene, Input, and Pan & Zoom tabs

If an option is dimmed, it is not available for the current grid.

Reset All: Resets all items to the defaults.

Reset Scale: Resets the scale to the defaults.

Reset Position: Resets the position to the defaults.

Reset Angle: Resets the angle to the defaults.

Rotate +90: Rotates the grid 90° clockwise.

Rotate -90: Rotates the grid 90° counter-clockwise.

Rotate 180: Rotates the grid 180°.

Flip Vertical: Flips the grid vertically.

Flip Horizontal: Flips the grid horizontally.

Zoom In 2x: Zooms in on the current grid to 200%.

Zoom Out 2x: Zooms out on the current grid to 50%.

Items on the Virtual Sets, Backgrounds, Output Clips, Sessions, and Browse library tabs

If an option is dimmed or not present, it is not available for the current item.

Open: Opens the selected file.

Play: Plays the selected video file.

Copy: Copies the file to clipboard.

Delete: Deletes the file from storage (e.g., hard disk).

Rename: Opens the name field for editing.

Blank spot on one of the library tabs

If an option is dimmed or not present, it is not available for the current item.

Paste: Pastes the file from the clipboard.

Create New Folder: Creates a child folder in the current folder.

Set Current Folder As Home For: Makes the current folder the default for the current library.

Reset Default Home Folder For: Reverts the default folder to the application default for the current library.

Creating and managing Ultra sessions

In Ultra, a session is the basic framework within which you work to create a composited movie. An Ultra session is very similar to a *composition* in Adobe After Effects. Each session contains multiple layers that are composited together, and each of these layers has a video, image, or virtual set file that it refers to for source content. In each session, you specify settings, such as the keyer settings. When you save a session, Ultra creates a file with an extension of .mks that stores information about the inputs and settings.

Creating a session

To create a session, choose File > New > New 4:3 Session (Ctrl+N) or New 16:9 Session (Ctrl+W). The choice of session type sets the frame aspect ratio on the Output tab. The session's frame aspect ratio also affects the Input Preview Monitor and Output Preview Monitor, as well as the grid controls on the Scene, Pan & Zoom, and Input tabs.

Changing the default virtual set

The default set is Simple Keyed Clip.mfx or Simple Keyed Clip 16x9.mfx, depending on whether the session is a 4:3 or 16:9 session. To change the default virtual set, choose Tools > Application Settings (or press F3), and then click the Browse button to select the virtual set.

Opening a session

To open a session, click the Sessions tab, and double-click the thumbnail image for the desired session.

If you prefer to work through a standard Windows dialog box, then choose File > Open Session or press Ctrl+O. The dialog box displays only folders and Ultra session files (.mks). Browse to a session, and either double-click it or select it and press Enter.

You can also open a session by double-clicking the .mks file in any file manager (for example, Windows Explorer) or by dragging and dropping the file from a file manager to Ultra.

By default, Ultra opens a new, blank session. If you prefer to have Ultra open the last session, choose Tools > Application Settings (or press F3), and select Start Up In Last Session.

To open a recently open session, choose File > Recent Sessions.

Saving a session

To save a session, choose File > Save Session, or press Ctrl+S. The first time you save a session, a dialog box appears in which you can enter a name for the session and select the location to which the session is saved.

NOTE

Saving a session has nothing to do with saving or rendering a composited output movie. For more information, see [“Saving the finished video” on page 119](#).

Changing the default session's path

The default folder for saving sessions is \My Documents\Adobe Ultra CS3\My Sessions, which is also the default path for the Sessions tab. Each time you save a session, the path to which you save the session becomes the default path for new sessions.

Saving a copy of a session

Saving a copy of a session is an easy way to back up your work or create a new session that uses some of the same input assignments or settings as an existing session. To make a copy of a session, choose File > Save Session As, and save the session with a new name or to a new location.

Working with a session on a different computer

When you copy or move a session from one computer to another, you must transfer the .mks file and any source files that are used in the session but not included as part of Ultra or an installed Master Sets Library. The source files must be where Ultra expects to find them.

If sources are in the default, \Program Files\Adobe\Adobe Ultra CS3\Content location, then Ultra can find them. If the session uses any files that are not stored in the Content folder, then you must save them to the location with the identical path on the second computer. For example, if the files were in the Custom Ultra Content folder in My Documents, then you must replicate the full path, including the username. Alternatively, you can save the files wherever you want to on the second system, and then reassign the affected sources.

Creating and assigning sources and virtual sets

This section describes how to prepare graphics and video clips for use in Ultra, customize the sets that come in the Master Sets Libraries, and assign graphics and virtual sets within a session.

Shooting video for Ultra

With the sophisticated keying technology built into Ultra, you can make use of even poorly shot source footage. Even so, the better the quality of the input, the better the resulting key will be. In fact, Ultra simplifies or eliminates so many of the technical problems associated with keying that the biggest remaining factor in achieving excellent output is the quality of the input clip, in particular the color and saturation of its background.

Live Preview

Using the Live Preview feature, you can preview the video feed from the camera as the input clip, composited in real time while you are shooting. Connect the camera to the computer and choose Live Preview from the list under the Input Preview Monitor to use the live feed from the camera as the input clip. You can then set the key as you normally would and check for problems such as hotspots, wrinkles, shadows, and color spill from the background onto the subject. This helps you to evaluate whether the current lighting, background, and framing will key well and work with the intended virtual set when keyed later in post-production.

Live Preview is intended only for evaluating the setup before recording clips. Ultra does not support real-time keying output of a live source.

Switching to Live Preview does not affect the input clip assignment, if there is one. In fact, you can use the list under the Input Preview Monitor to toggle between Live Preview and the current input clip.

To configure Live Preview, choose Tools > Application Settings, and modify settings as needed:

For Ultra to use a DV camera for Live Preview, the camera must be on and connected via an OHCI-compliant IEEE-1394 port before you start Ultra. The camera must be recognized by the computer as a video device. You can verify that the camera is recognized by looking for the camera as a device in the My Computer area in Windows. If the camera doesn't appear, then the computer may have detected more than one video input source. In this case, you must choose the correct device from the Device list in the Application Settings dialog box.

Because decoding DV in real time requires a lot of processing power, Adobe recommends that you use a fast computer. On slower computers, you may need to lower the Resolution value, which controls the preview resolution.

Some video cameras output thin black bars in the overscan areas on the right and left edges. You can change the Underscan value in Ultra to delete these bars. Ultra stretches the image by the specified amount, preserving the frame aspect ratio of the live input. This setting applies only in Live Preview mode.

Setting up the camera

You should always disable automatic color settings on the camera when shooting for color keying. Otherwise, the background's brightness or hue may change when on-camera subjects move across the frame. Adjusting the camera manually, try to match the intended virtual background as closely as possible by adjusting the iris, white balance, shutter speed, and other camera-specific parameters.

Ultra works best when the camera is locked down on a tripod. In most modes, Ultra uses a static model of the background. If the camera moves, then the model will not remain aligned with the variations in the background. If a clip involves any camera movements, then the only way that you can key it in Ultra is with the single key point method, which works entirely by color without a model. For more information, see [“Single Key Point Method \(One Color Pickup\)” on page 79](#).

Controlling the lighting

Controlling the lighting of the foreground scene helps you to achieve realistic results. The goal is to adjust the foreground to match the intended virtual background. Analyze the intended background—either a virtual set or your own still image or video clip—to determine the direction of the primary light source for the background scene. Position the lights at the same relative positions so that the subject receives the same general lighting as elements in the background. For example, if the background is strongly lit and leaves hard shadows and shiny highlights, then you want comparable lighting on the subject in front of the color screen. Getting the subject's shadow right can significantly enhance the realism of the final composited shot.

Although you can tune the key to preserve shadows from the input clip, you can also generate shadows digitally by using Ultra. This approach has several advantages over working with actual shadows. Most notably, you can easily control the shadow's position, scale, and opacity as well as several other attributes. For more information, see [“Adding shadows and reflections” on page 111](#).

After you adjust the lighting and camera settings so that the input clip matches the virtual background as closely as possible, you can bring them closer still by performing color corrections in Ultra. You can color-correct each layer independently. Sometimes adjusting the color of the background to match the input clip can yield better results than correcting the keyed input clip itself. Often a combination of both is ideal.

Framing the subject

Set the angle, height, and field of view for the camera to match the characteristics of the virtual background that you are using. It's always best to frame the subject as tightly as possible for the selected background. This maximizes the resolution of the image, which translates to higher quality. By contrast, if you shoot the subject with a larger field of view than you are using, you'll end up cropping and probably scaling up the remaining image, thereby throwing away a substantial portion of the camera's resolution. Scaling down an image that's too large preserves quality, and scaling up an image that's too small degrades the image.

Virtual sets from the Master Sets Libraries are designed to work best with input clips of a particular framing. The main standardized framings are tight, medium, and wide. The names of nearly all of the virtual sets in the Master Sets Libraries indicate the framing for which they are designed. The consistency of framing across the Master Sets Libraries provides a valuable advantage. The scale and position of the subject are preset for each virtual set. Therefore, you don't have to think about the scale of the subject in the final composited scene when shooting. For example, if the set shows a full-body view of a person who's scaled down and positioned on a stage, you should still shoot with the standard wide framing (with the person's head near the top of the frame and their toes near the bottom). Don't try to frame subjects as they will be positioned in the final composited scene; the set will handle the scaling automatically. One of the advantages of shooting to the three standardized framings is that you can use a shot with a given framing in any set designed for that framing. This allows great flexibility in post-production.

The following is a key to the main scales to which you should shoot.



A) Tight: Close-up shot, approximately from the chest up B) Medium: Medium-distance shot, approximately from the waist up C) Wide: Wide-angle, full-body shot, with space above and below the subject

TIP

If the subject is a person who's standing or sitting and won't move much or gesture widely, try shooting with the camera turned sideways to make maximum use of the camera's resolution.

Always shoot the subject centered within the frame laterally—or at least not cropped on either side. If the subject is partially out of the frame in the composited layout, it's easy to move the layer to the side. Conversely, if you crop an arm at the shoulder while shooting and later decide that you want to position the subject more toward the center frame than you anticipated, you can't put the arm back in the frame.

Optimizing the color screen backdrop

A high-quality color backdrop that is properly lit yields superior results. There are several aspects to a good backdrop.

Color and finish: Adobe recommends green as the best backdrop color for typical Ultra usage. In some cases, however, green isn't the best backdrop color, and other colors will work. For example, if your subject must wear green clothing, you may get better results with a blue screen. In general, the best key color is a color that is not used in your subject. If you use key color paint, apply several coats and allow adequate drying time to increase color saturation. If you use an improvised backdrop material, ensure that the color is deeply saturated and that the surface has a smooth matte finish. Avoid shiny or textured surfaces.

Flatness: If you use a cloth or plastic sheeting, reduce the wrinkles as much as possible. A hand-held clothes steamer can be helpful. For a free-hanging cloth, stretch it tight enough to remove the folds and prevent rippling from air currents. You can use the elastic straps with clips designed for holding bedsheets to mattresses for this purpose.

Lighting: Whenever possible, light the backdrop separately from the foreground subject. This requires moving the subject as far from the backdrop as possible to create space for two separate lighting zones that don't interfere with each other. If this brings areas beyond the edges of the backdrop into view, you can delete them with Mask Painter tool or by cropping the edges. Just keep the subject entirely in front of the backdrop. For more information, see [“Painting a mask” on page 84](#) or [“Cropping the edge of a frame” on page 84](#).

Lighting on the backdrop should be as even as possible, without hotspots or shadows. Umbrella reflectors and soft box diffusers are ideal for providing the desired results. A light meter or in-camera zebra pattern indicator can help ensure that the backdrop is evenly lit and deeply saturated.

TIP

For each clip that you record and then key and composite in Ultra, ensure that you get at least a few frames that show only the keying background as it will be lit and framed for the shot. Frames with nothing in the foreground let you use the Set Key method, which not only produces the highest quality key but is also the easiest to use. For more information, see [“Set Key” on page 78](#).

Reducing spill

Colored light spilling from the background onto the subject can interfere with getting a convincing key. Although spill suppression features in Ultra can greatly reduce color spill problems, being careful while you're shooting is better yet. Keep the following points in mind:

The larger the background, the more significant this issue tends to be. That's because every square inch of colored background reflects light of the background's color.

In wide shots with the subject standing on a color screen, the floor also becomes a source of bounced light. To minimize spill from the floor, reduce the amount of key color flooring in front of the subject. One way to accomplish this is to place a black drop cloth immediately in front of the farthest point forward that the subject's feet will reach. You can use the Input Cropping controls to trim out everything in front of the subject's feet.

A nearby white wall beside the background or behind the camera can compound the problem by bouncing more colored light back onto the subject. To minimize this problem, set up the key backdrop in an area without nearby light-colored walls.

Choosing the subject's wardrobe

Ultra does not know whether a green pixel is part of the backdrop or the subject's necktie, so ensure that the subject isn't wearing anything that's too close to the color of the backdrop. Otherwise, you'll be looking right through the subject to the virtual set behind.

Choosing the background or virtual set

The best results are achieved when the virtual background and the subject are similar not only in brightness but also in color saturation, hue, and contrast. When selecting a background or virtual set to be digitally inserted behind a particular foreground subject, look for one that will match reasonably well in these regards. You can apply color correction settings in Ultra to make sources match even better, but it's best to not rely on digital color correction to make divergent sources match exactly.

Directing on a virtual set

Performing in an imaginary environment can be challenging for the actor portraying your subject. Powerful technology like Ultra now means that the subject must not only get into character but also into location. Actors tend to perform differently depending on the size of the space they are in and how far away the camera is. Now that you can digitally manipulate these aspects with such ease, actors will need some coaching and feedback to help them work with the virtual environment during shooting. You should encourage the subject to look around the environment and gesture to virtual objects such as on-set monitors as appropriate. If they are going to be digitally scaled down to simulate a far-away camera, the subject must project their voice as they would when performing to a far-away camera. If the subject will be inserted into a large virtual environment with a distant camera, they may want to be more expressive with their arms and entire body.

Details help complete an illusion. How the subject is dressed and what props they're holding can sell the scene to the audience and help the actors hold their mental image of the virtual environment. If the virtual background will be footage of a hot day at the beach, for example, you may want to consider adding a little sweat to the brow or some ocean breeze from an off-camera fan.

Improving the quality of the source footage and facilitating recording

Adobe® OnLocation CS3 can take a lot of the guesswork out of recording video that will key well. OnLocation provides tools that will help you improve the quality of the video that you shoot. Two tools in particular, the Waveform Monitor and Vectorscope, can be invaluable when you're recording footage that you will then key in Ultra. These tools digitally analyze every pixel of every frame in the video stream and graphically display the brightness, color, and saturation. With this information, you can adjust the camera settings, lighting, and other variables in the shooting environment to achieve the cleanest, most consistent background possible. OnLocation also lets you record clips directly to an internal or external hard disk. As soon as you stop recording, you have a digitized input clip ready to drop into Ultra. Even if

you don't actually set up the whole session and render out the composited footage, you can at least set the key in a minute or less to confirm that all will go smoothly during post-production. To learn more about OnLocation, go to the Adobe website (www.adobe.com), and download a free trial version.

Assigning content to layers

This section explains how to assign a source to a layer and addresses some of the fine points of dealing with sources.

Assigning source content to a layer

Ultra provides several methods for assigning an image, video clip, or virtual set to the appropriate layer. Most of these methods apply the selected source to the active layer. For more information, see “Active layer” on page 24. If the correct layer isn't selected, either click its layer thumbnail or use the list under the Input Preview Monitor. For the inset and overlay layers, you may also have to choose the desired layer (Source B, C, and so on; or Overlay 1, 2, and so on) by using the list above the layer thumbnail. After the layer is selected, any of the following actions assign a source to it. These methods also work for assigning a virtual set.

Double-click the source's thumbnail image in a library tab. When you double-click the thumbnail image for a still image or video clip on one of the tabs, that image or clip is assigned as the source for the active layer. Double-clicking a virtual set, however, assigns it to the Virtual Set layer, regardless of which layer you select.

Right-click the source's thumbnail image in a library tab, and choose Open.

Drag the source's thumbnail image from a library tab onto the Input Preview Monitor or Output Preview Monitor.

You can assign a source to any layer, regardless of which one is active, by dragging and dropping the source's thumbnail image directly on the layer's thumbnail. As with the previous options, you may need to select the specific inset or overlay first. Assigning a source to a layer by dragging the source to the layer thumbnail does not make that layer the active layer.

Changing sources for a layer

The methods outlined previously work regardless of whether a source is already assigned to the layer. When you change the source assignment, the new source inherits most of the adjustments to the layer that were made on any of the tabs. The only exceptions are the In and Out points for trimming a video clip. This lets you experiment with different combinations without having to redo any of the settings. For example, you can review multiple takes of a given shot quickly and easily. If the source that you substitute differs substantially in lighting or key color background from the source that you originally keyed, you must recalibrate the keyer.

You can change to a white, black, or checkerboard source by using the right-click menu for the layer thumbnail.

With virtual sets, the assignment of sources to inset layers is preserved, even if you switch to a set that doesn't have all of the insets. If you later change back to a set that includes those sources, you do not have to reassign them. However, the scale, position, and orientation settings for the input clip and inset sources are overridden by those that are predefined for each virtual set.

NOTE

If you are creating several composited clips for a single scene within a given Master Set that has insets or to which you're adding overlays, you can eliminate the need to assign the same set of sources to those layers each time by copying the sessions. Rather than creating each related session from scratch, make a copy of one that's already set up. You can then switch the virtual set and input clip, preserving the assignment of sources to inputs and overlays. You must still assign sources to any layers that didn't exist in the session that you copied.

Unassigning content from a layer

If for any reason you want to remove a source from a layer, which leaves the layer blank, right-click the layer thumbnail, and choose Unload Source or Remove Current Overlay.

This option isn't available for the virtual set because something must be assigned at all times. If you want to delete the current set, you must assign another set.

To remove a virtual set and return to the default, select the Simple Keyed Clip virtual set found in the Basic folder of the Virtual Sets tab.

Setting the aspect ratio of the input source

When you assign a video clip as a source, Ultra tries to determine its native aspect ratio but is sometimes unable to do so. If a clip or still image appears stretched or squeezed, you can correct it by selecting the correct setting from the Aspect menu on the Input tab.

Inputting sources that use film alpha, such as Avid (Invert Alpha option)

Video systems conventionally interpret an alpha channel value of 0 to indicate complete transparency. Film systems conventionally interpret an alpha channel value of 0 to indicate complete opacity. When importing a video source from a system that uses film alpha (such as Avid), use the Invert Alpha option on the Input tab.

Set the field order (interlaced video clips only)

Interlaced video is divided into alternating fields, called *upper* and *lower*. Field order specifies which field of interlaced video is drawn to the screen first. You must ensure that the field order setting for each interlaced video clip is the same as that clip's native field order.

Standard-definition video (such as NTSC DV) is typically lower-field first, whereas PAL D1 and many high-definition formats (such as DVCProHD 1080i) are upper-field first. If you choose the wrong field order for a clip, you'll see a comb-like edge around the subject and stuttering with movement in the image.

1. Assign the video clip to the desired layer, and select it as the active layer.
2. Select the appropriate setting from the Field Order list on the Input tab.

Matching the aspect ratio of a basic set's background with a session

Each virtual set has a native aspect ratio. In most cases, you should match the aspect ratio of the set to the aspect ratio of the session that is specified on the Output tab. However, Ultra lets you mix them if that suits your purposes.

Matching input clips and virtual sets

You should match each input clip with a virtual set that roughly matches the framing. For most virtual sets, the title indicates the framing, with Tight, Medium, or Wide in parentheses. The exceptions are VirtualTrak sets, which are designated as Trak, and sets where the input clip appears as an inset, which have nothing in parentheses in the titles. For VirtualTrak sets, you must preview the tracking shot to determine its framing. For sets that display the input clip as an inset, any framing works.



A) Tight: Close-up shot, approximately from the chest up B) Medium: Medium-distance shot, approximately from the waist up C) Wide: Wide-angle, full-body shot, with space above and below the subject.

Adding overlay layers

You can add up to four overlays to any session, regardless of whether the virtual set has one or more foreground elements. By default, one empty overlay layer exists in each session. To add an overlay, right-click the thumbnail for an existing overlay that has a source assigned, and choose Add New Overlay. This option is unavailable if the current overlay has no source assigned or if four of these layers already exist.

Using a still image as the input clip

You can assign any supported graphic format as the input clip, key it, and then output a composited still image or video clip.

To output a still image, use the Frame Sequence format. For more information, see [“Outputting still images \(Frame Sequence\)” on page 122.](#)

Panning and zooming over an entirely still scene: If the input clip and all of the other sources are still images and you want to output a video clip in which the action is a virtual camera move across the composited scene, then the input clip must have a duration. Select the input clip as the active layer, or any other layer, and enter a time in the Out Point field on the Input tab. If you're not yet certain exactly how long the session will be with the virtual camera moves, set a value higher than you expect to use, and then reduce it after you apply all of the camera moves.

Supported input formats

Ultra supports HD and HDV video, QuickTime video files, and an expanded list of graphic formats. The following table provides a partial list of supported video and graphics formats. The list isn't complete because compatibility depends in part on what codecs are installed on the computer.

Format	Resolution (frame dimensions)	Frame rate
High definition (HD and HDV)	1080i 1080p 720p	NTSC: 60i and 30p PAL: 50i and 25p Film: 24p (nonpulldown)
Standard definition (SD) Uncompressed 24-bit	NTSC: 720x480 and 720x486 PAL: 720x576	
Uncompressed 32-bit AVI (with alpha)		
DV AVI Type 1 (audio and video on separate streams)		
DV AVI Type 2 (audio and video on the same stream)		
MPEG-1, MPEG-2 (.mpg, .mpeg, .m2v, .m2t)		
QuickTime (.mov)		
Windows Media (.wmv)		
Adobe virtual set (.mfx)		

Format	Resolution (frame dimensions)	Frame rate
Still images .bmp .jpg .png .ppm .tga .tiff	up to 4096x4096 (graphics card permitting)	

When you ran Ultra for the first time, you chose either NTSC or PAL. Regardless of which video format you chose to work with, you can use video clips of either format as sources.

You can use still images with dimensions of up to 4096x4096 pixels as sources if the graphics card supports that resolution. Ultra preserves the native resolution of all graphics sources up to 4096x4096. One advantage of this is that when you zoom in the image remains crisp and unmarred by the blockiness the comes from enlarging low-resolution graphics.

In general, however, the format of the video clips and the dimensions of the still images used as sources should be consistent with the video format in which you'll output the finished clips.

NOTE

If you assign a video clip to any layer other than the input clip, you may need to trim it or set it to loop so that it ends at the same time as the input clip, if that's your goal. For more information, see ["Trimming the In and Out Points in a video clip" on page 104](#) or ["Looping the clip" on page 105](#).

Creating elements for a set or individual layers

Virtual sets are bundles of visual elements that work together to produce the illusion of a three-dimensional set. The virtual sets that come in the Master Sets Libraries are advanced designs. Some of these virtual sets have foreground elements and multiple insets, each with a letter designating which source it is. The Basic sets that are installed with Ultra let you achieve comparable results using your own graphics for background and foreground elements. You must apply an alpha channel where you want transparency through to the next layer in the composited scene.

This section explains how to create the elements that make up a virtual set. The principals are the same regardless of whether you're working in an image-editing application such as Photoshop or a 3D application such as Maya™ or 3DMax™. Keep the following general pointers in mind as you proceed:

Supported file types: PNG, JPEG, BMP, PPM, TIFF and Targa (TGA).

Transparency: Save any layer that has transparent regions in a format that supports an alpha channel, such as .png and .psd files. To learn more about alpha channels and how to save layers in a format that preserves transparency, see the image-editing application's documentation.

Perspective: Shoot the still images that you're using for a set from the height and angle that you're using for the main subject. If you're using computer-generated graphics, design them with the camera's perspective in mind.

Lighting: Light the scene from the same angle from which you're lighting the subject when shooting the input clip.

Multiple angles: If you have multiple scenes with different angles of the same set, you must prepare the images from each angle. For the most consistent, realistic appearance, light all of the sets from the same absolute or global perspective.

Aspect ratio: Ultra does not force images to the 4:3 aspect ratio.

TIP

To achieve more advanced results:

- To produce a dynamic result like those from VirtualTrak shots from the Master Sets Libraries, use the pan and zoom features. For more information, see [“Panning and zooming” on page 99](#).
- To show the input clip as an inset, create an overlay with an alpha region where you want the keyed input clip to appear, and then scale and position that clip and its background to fit in the designated space.

Backgrounds

There are two basic types of backgrounds: background with one or more transparent regions cut in it to show the sources behind it, and backgrounds without transparent regions.

Backgrounds without transparent regions are simple to create. You can assign any image of a supported file type as a background. As a rule, you want the frame aspect ratio for the background to be the same as that for the session as set on the Output tab.

For backgrounds that you use with one or more inset sources, you must create an alpha (transparency) region in the image for each inset. In Photoshop and other image-editing applications, this can be accomplished in many ways, including using masks.


If the alpha region is on in a surface that is angled to the plane of the camera's lens, then you should adjust the perspective of the alpha region accordingly. You typically need to change the size, position, and possibly orientation of the inset source to appear in the correct space. For more information, see [“Changing the position and scale of a layer plane” on page 92](#) and [“Changing the orientation of a layer plane” on page 93](#).

When you create the alpha region, it is often best to draw a frame around it, as well, such as the pink border drawn around the alpha region in this example.



Overlays

The foreground element can be any object or structure that you want to appear in front of the subject for at least part of a scene. The foreground could be a prop such as a chair that lends dimension or a door that the subject emerges from behind. In the following example, the foreground is a desk.



For photographs, you can either copy the overlay from the background and paste it back in as a separate layer or add an object from another image. If you're drawing the elements in an image-editing or 3D application, then you should put each element on its own layer.

For videos, you can use Ultra to create the keyed overlay.

1. Record the clip as you would any clip to be keyed in Ultra (that is, against a green or blue background).
2. Open the clip in its own session, and key it as usual.
3. Save the clip with the following settings on the Output tab:

Format: DirectShow AVI

Codec: Uncompressed

32 bit AVI with Alpha

4. The clip is in the Output Clips folder, or the path that you set for it. Assign the clip to the overlay as you would any source.
5. Proceed with any resizing, repositioning, and so on.

TIP

If you're working with a photographic image, a quick way to isolate the image with alpha all around is to shoot it against a greenscreen and then delete that background in Photoshop.

NOTE

If you want to have two or more objects in the foreground, you can put them in a single image. Be aware, however, that they will move as a unit if you change their size, position, or orientation.

Finished, composited scene

The following is an example of what the finished, composited scene looks like.



This example illustrates a common problem that ruins the illusion of the composited scene. The subject's toes are in a position where the overlay does not cover them. You have several options for remedying the problem:

Include the area within the pink circle as part of the overlay image.

Use the Mask Painter to make that region of the input clip transparent. For more information, see [“Cropping and spot masking the source clip” on page 83](#).

Reposition the subject a few pixels to the left. For more information, see [“Changing the position and scale of a layer plane” on page 92](#).

Depending on the scene and where the subject walks, you may also be able to use the Input Cropping controls. For more information, see [“Cropping the edge of a frame” on page 84](#).



If the overlay covers part of the subject that should be in front and repositioning is not an option, then you may need to split the scene in two, and delete or adapt the overlay in the second part. For example, assume that there's a doorway behind the subject and the area from the door frame to the left is part of the overlay to create the illusion that the subject is entering the scene through that door. It's likely that the subject's right hand would be behind the overlay when gesturing. For instructions on getting around this type of situation, see [“Advanced compositing tasks” on page 72](#).





Advanced compositing tasks

You may want or need to have an element in the foreground in one segment of a scene but in the background in another segment. Moving all or part of an image from the foreground to the background, or vice versa, can help you to get the subject on the correct side of a wall, doorway, or pillar. This can also help create the illusion of dimension within the scene.

All of the overlays in a particular session are always in front of the subject. However, you can achieve this illusion of dimension by breaking the scene into two or more sessions. You can then use the same input clip in each session, trimming it appropriately by setting the In point and Out point so that the segments blend seamlessly. You should break the sessions at a timepoint where the subject is not in front of or behind the element that is swapping layers. For more information, see [“Trimming the In and Out Points in a video clip” on page 104](#).

The images below represent a three-part scene.

Trim times	Overlay	Composited shot
In Point: 0:00.00 Out Point: 0:10.00		

Trim times	Overlay	Composited shot
In Point: 0:10.01 Out Point: 0:20.00		
In Point: 0:20.01 Out Point: 0:40.00		

Because saving clips in Ultra is fast, particularly if you use the GPU Boost feature, you may find it quicker to render the complete scene multiple times—once with each overlay—and then use an NLE to cut from one scene to the next. This achieves the same result without having to create multiple sessions in Ultra and trim the input clip precisely in each session. Which workflow is faster depends on the speed of the computer, the size of the scene, and other factors.

If you reposition the overlay in one session, then when you merge an object from the overlay into the background for another session, you will have to move the object to the same relative position. Otherwise, the object will appear to move when you cut from one session to the next. If you left the element in the background when you copied it for an overlay, then you'll have to reposition the element in the foreground and background for the same session or else they'll be out of registration.

For more information, see [“Positioning insets in custom virtual sets” on page 94.](#)

Customizing a virtual set

You can modify a virtual set by changing the color, size, orientation, and other parameters in Ultra, or you can use an image-editing application to redesign any or all of an image.

Editing virtual set images

The source files that make up the layers of a static virtual set are .jpg and .png files that you can modify in any image-editing application. However, you cannot edit VirtualTrak sets. If you are using any VirtualTrak shots, then before you change a set, you should storyboard all of the scenes in a given master set and avoid editing any static views that are visible in the VirtualTrak shots. This avoids breaking the continuity of the scene.

CAUTION

The licensing agreement for Ultra prohibits the resale of modified virtual sets and assets. In other words, you are not permitted to change the color or the value of some other property of virtual sets and then post the content for sale as original content. The license allows users to change the image slightly for their own productions.

A virtual set has one or more image source files that are normally hidden. To determine the names of the files that you want to revise:

1. Load the desired virtual set.
2. Switch from the standard set of thumbnail controls for User-Defined sources to those for the Pre-Defined sources for virtual sets by choosing View > Displayed Inputs > PreDefined or by pressing Alt+P. The top thumbnail is for the virtual set just as it is for the standard controls. Below it is a thumbnail for each layer in the set. (To return to the standard set of layer thumbnails, choose View > Displayed Inputs > User-Defined or press Alt+U.)
3. Click the thumbnail for the layer that you want to modify.
4. Check the Current Source field below the Input Preview Monitor to find the name of its source file. You can check the full path in the Look In field of the dialog box that appears when you click the Browse button.

The files that you just identified are stored in the Elements folder in the Master Set folder for the selected virtual set.

1. Browse to where the virtual sets are stored. The default path is C:\Program Files\Adobe\Adobe Ultra CS3\Content\Virtual Sets\[*Master Set name*].
2. If you want to keep a version of the Master Set in its original form, copy its entire folder.
3. If you don't see the Elements folder in the Master Set folder, choose Tools > File Options in Windows Explorer, click the View tab, and then select Show Hidden Files And Folders.
4. If you did not copy the entire Master Set folder, then Adobe recommends that you either make a copy of the Elements folder before starting to edit any images, or save the changes by a new name. Failure to do so could necessitate reinstalling the Master Sets Library to return to the original images for the virtual sets.

After you access the Elements folder, the .png and .jpg files are available for you to open and edit in an image-editing application.

How you incorporate customized graphics into an Ultra session depends on whether you save the revised graphics by their original file names or by new names. If you used the existing file names, then assigning the associated virtual set loads the images. If you saved with new file names to preserve the original image files, then you must assign the new sources through Ultra as follows:

1. Assign the appropriate virtual set.
2. Switch to the Pre-Defined Sources view (Alt+P).
3. Select the thumbnail for a layer that you want to change to your version of the image.
4. Assign the desired image source as you would any other source. For more information, see [“Assigning content to layers” on page 63](#).

Moving virtual sets to an alternate location

When you install a Master Sets Library, it is automatically stored in the same place that you installed Ultra. By default, the path is C:\Program Files\Adobe\Adobe Ultra CS3\Content\Virtual Sets\. After the installation, you can move some or all of the virtual sets to an alternate drive.

Moving a Master Set or the complete Virtual Set Library is the same as moving any folder using Windows Explorer or your preferred file management utility.

Copying a single virtual set

Copying a single virtual set is problematic because the component graphics for all of the sets in a Master Set are in a single, central folder. Therefore, you must isolate the files that are associated with the particular virtual set that you want to copy. Because some graphics are used in two or more virtual sets, it is important that you copy, not move, files in this operation.

1. Switch from the standard set of thumbnail controls for User-Defined Sources to those for the Pre-Defined sources for virtual sets by choosing View > Displayed Inputs > Pre-Defined or by pressing Alt+P. The top thumbnail is for the virtual set just as it is for the other set of controls. Below it is a thumbnail for each layer in the set.
2. Click each thumbnail, and check the Current Source field below the Input Preview Monitor to find the name of its source file. You can check the full path in the Look In field of the dialog box that appears when you click the Browse button.
3. In Windows Explorer, browse to the appropriate folder for the Master Set, and copy the .mfx files for the desired virtual sets.

4. Open another Windows Explorer window, browse to the location where you want to save a copy of this virtual set, and create a folder with a name of your choice.
5. Paste the .mfx files into the new folder.
6. Create a subfolder within the new folder called Elements.
7. Return to the first Explorer window, and look for an Elements folder. If you don't see it, choose Tools > File Options, click the View tab, and then enable the Show Hidden Files and Folders option.
8. Open the Elements folder, and copy all of the files associated with the desired virtual sets.
9. Paste these files into the Elements folder that you created in the second Explorer window.

Setting the key

Ultra is a professional-grade keying tool capable of producing outstanding compositing results, making excellent background replacement possible with minimal effort. Because of the vector processing that Ultra performs, you can achieve excellent results even with source video that is less than perfect.

Ultra provides three methods of setting the key. The method that you should use depends on several factors. The following procedure should help you determine the method to use and whether additional manual refinements are necessary.

1. If the color of the background is not well saturated, first enhance the color of the background.
2. If there is at least one frame with just the background, use the Set Key Method. If not, continue to Step 3.
3. If the color of the background is very consistent, use the Single Key Point method. If the color is not consistent, use the Multiple Key Points method.
4. After applying the appropriate keying method, fine-tune the key if necessary.

Keying methods

Set Key Method: This method produces the best results and is also the easiest to execute. However, you must have at least one frame in which only the background is visible. For more information, see [“Set Key” on page 78](#).

Single Key Point Method (One Color Pickup): This method works well with backgrounds that have a consistent, saturated shade of green or blue. For more information, see [“Single Key Point Method \(One Color Pickup\)” on page 79](#).

Multiple Key Points Method (Color Spread): If you don't have a frame with only the background visible and the color, brightness, and saturation of the background are not consistent throughout the frame, then use this method to create the chroma key map. To preserve shadows from the input clip, you also set multiple key points. For more information, see [“Multiple Key Points Method \(Color Spread\)” on page 80](#).

If you have a video card that supports Pixel Shader 2.0, Ultra provides a feature that substantially accelerates how fast the system keys and composites a clip during a preview and in the course of saving output movies. Ultra can use the graphics processing unit (GPU), which greatly reduces the load on the CPU. To take advantage of this advanced capability, enable GPU Boost on the Keyer tab.

Adobe recommends the following models of graphics cards or better:

Make	SD video	HD video
ATI	Radeon 9600	Radeon 9800
NVIDIA	GeForce FX 5700	GeForce 6 Series 6600

Improving a background in the input clip

If the background of the input clip that you are working with is washed out to such a degree that you can't get a decent key, you can use the Pre-Processing controls on the Colors tab to improve the quality. You may not recognize this problem until you've tried unsuccessfully to get a good key. After you become familiar with what you can accomplish with the keyer, you'll know at a glance when color adjustments are necessary.

1. Select Pre-Processing on the Colors tab, and select Enable.
2. Increase the Saturation setting. This makes the background more keyable, but it also causes problems with the colors in the subject.
3. Proceed with keying the clip as normal.
4. Select Post-Processing on the Colors tab, and select Enable.
5. Reduce the Saturation setting to achieve a natural look.

TIP

Although you may be able to rescue an otherwise problematic clip by changing the color, you should consider this your last resort, because it tends to produce artifacts and it involves more work. The results are better if the background in the input clip is well saturated and well lit to begin with. If you have any influence on the filming process, do whatever you can at that stage to capture footage that will be easier to key properly in Ultra. If you're not sure what it takes to achieve high-quality footage, see [“Shooting video for Ultra” on page 57](#).

Set Key

Set Key is the recommended means for keying, not only because it produces the best results, but also because it's easiest. At the click of a button, Ultra analyzes the entire frame and generates a mathematical model that it uses to key out the background for the session.

To use this method, the clip must have at least one reference frame, which is a frame that shows only the color screen background with nothing in the foreground. The frame can have areas beyond the edges of the color screen, because you will mask them out later.

The reference frame does not actually have to be from the input clip that you will be compositing. The most important thing is that the lighting, framing, and state of the backdrop for the reference frame and the actual input clip are identical. As long as none of these factors are different, the reference frame can come from another clip. If conditions on the set are static and reasonably under your control, you could shoot one clip to provide the reference frame for multiple clips with the same framing. If, however, any elements change—for example, a wrinkle in the backdrop appears, disappears, or migrates a few inches—then you need a new reference frame for subsequent input clips.

NOTE

If you're seeing a ghost image, then you probably clicked the Set Key button with the subject in the frame. This method works only when the frame is free of anything in the foreground.

To resolve this problem, either drag the preview slider to a show clear reference frame and click Set Key again, deselect Enable on the Keyer tab, or use one of the Key Point methods. For more information, see [“Setting Key Points \(Apply Points Method\)” on page 79](#).

The Set Key Method works only if the framing of the camera remains constant throughout the shot. This means no zooming in or out, no panning or tilting, no moving boom or dolly shots, and no handheld camera. If you want these types of results, keep in mind that you can accomplish them in Ultra by using virtual camera moves. For more information, see [“Panning and zooming” on page 99](#).

To use the Set Key method, assign the clip containing a reference frame as the input clip and drag the preview slider to a reference frame. Then click the Set Key button. You don't have to select Enable first, because the Set Key button automatically enables the keyer.

The background should disappear to reveal the checkerboard in the Input Preview Monitor and the current background in the Output Preview Monitor. Also, the button changes from Set Key to Apply Points.

If the actual input clip is not loaded, assign it in place of the reference clip. Drag the preview slider through the session with the virtual set or background assigned, looking for points where the key is less than ideal. If you find any, then you must fine-tune the key. For more information, see [“Fine-tuning the Keyer settings” on page 84](#).

Setting Key Points (Apply Points Method)


Ultra provides two methods for setting the key using key points that you select. In general, you should only need to use one of these methods if you do not have a reference frame that shows only the color screen background with nothing in the foreground. If the background is a consistent, saturated shade of green or blue, then you should use the Single Key Point method. For more information, see [“Single Key Point Method \(One Color Pickup\)” on page 79](#). If the color, brightness, and saturation of the background are not consistent throughout the frame, then you should use the Multiple Key Points method. For more information, see [“Multiple Key Points Method \(Color Spread\)” on page 80](#).

Single Key Point Method (One Color Pickup)

You should use this method if you do not have a reference frame for the input clip and the keying background is well lit and consistent in color with no pronounced shadows or uneven shading. For more information, see [“Set Key” on page 78](#). If this is not the case for the current session, see [“Setting the key” on page 76](#) to determine which of the other two methods to use to set the key.

Unlike the other methods of setting the key, this method does not use a mathematical model. Instead, this method samples a single color and subtracts that from the entire image, hence the name One Color Pickup for the keying method.

To set the key

1. With the input clip as the active layer, click the Add Key Point tool  below the Input Preview Monitor. If this tool's icon is not displayed, then the input clip is not the active layer.
2. Click a single spot in the background to set the key point. Because the background should be a consistent color if you're using this method, it doesn't matter where you set the key point. If there are minor irregularities in the background, don't set the key point near them.
3. Click the Apply Points button or press Ctrl+K.
4. If necessary, fine-tune the key. For more information, see [“Fine-tuning the Keyer settings” on page 84](#).

Although the background should be consistent, it doesn't need to be exactly the same. Despite the slight vertical imperfections in the upper-left corner and a bit of variation in color, the frame in the following example is good enough to use for the One Color Pickup method. Using multiple points in this case would not significantly improve the quality of the key.



Multiple Key Points Method (Color Spread)

You should use this method in the following situations:


You do not have a reference frame for the input clip and the keying background is not a consistent color. For more information, see [“Set Key” on page 78](#).

You want to preserve the shadows from the input clip. For more information, see [“Keeping the shadow in an input clip” on page 82](#).

If neither of these conditions apply for the current session, then see [“Setting the key” on page 76](#) to determine which of the other two methods to use to set the key.

Whenever you apply two or more points, Ultra generates a mathematical model based on the differences between the points. For a background without pronounced discontinuities, three to five key points are normally sufficient, and their exact position is not critical. Backgrounds with problem areas, such as folds in the backdrop or corners where a wall meets the floor or another wall, will require more key points and greater care in positioning them.

To set key points for backgrounds with gradual gradients

1. With the input clip as the active layer, click the Add Key Point tool  below the Input Preview Monitor. If this tool's icon is not displayed, then the input clip is not the active layer.

2. Look for pools of darker and brighter screen color (blue or green) in the background, and click once in each of these regions to set the key points. In a dark pool, the key point should be where it's darkest. If there's a hotspot, the point should be where it's brightest. In the following example, the point in the lower-left corner and the two points on the far right side are for the three dark areas. The one next to the subject's head is for the whole center of the background, which is well saturated. The key point in the shadow causes the shadow to be keyed out. If you want to preserve the shadow, do not set any key points there.



3. Click the Apply Points button on the Keyer tab or press Ctrl+K.
4. If necessary, fine-tune the key. For more information, see [“Fine-tuning the Keyer settings”](#) on page 84.

To set key points for backgrounds with hard shadows

If the background has any distinct discontinuities in color or brightness, which often result from folds or deep wrinkles in the background or from angles where a wall meets the floor or another wall, then you must set key points along both sides of the discontinuity as shown in the following example.



In these cases, you'll achieve the best results if the key points are very close to the problem area, but not on top of it. To get a better look at what you're doing and have greater precision in positioning points, try magnifying the view of the Input Preview Monitor. For more information, see ["Input area and Input Preview Monitor" on page 28](#).

TIP

For a part of a problem area that the subject never passes in front of, masking the area generally produces better results. For more information, see ["Cropping and spot masking the source clip" on page 83](#).

NOTE

To delete the last point you added, press Ctrl+Z. To delete all of the points, click the Clear Points button on the Keyer tab, or press Ctrl+E.

Keeping the shadow in an input clip

A semitransparent shadow cast behind or below the subject can increase the realism of a composited shot. To preserve shadows from the input clip, use the Multiple Key Point method and take care not to position a key point within the shadow, as shown in the following example. For more information, see ["Multiple Key Points Method \(Color Spread\)" on page 80](#).



To change how pronounced the shadow is, adjust the Shadows slider in the Matte Generation area on the Keyer tab.

To eliminate any residual color from the screen (green or blue) from the shadow, increase Start Level.

Do not change the Shrink Matte setting, because it weakens the shadow and leaves artifacts.

If you're not satisfied with the real shadow, try a digital shadow. For more information, see [“Adding shadows and reflections” on page 111](#).

Digital shadows have the following advantages over real shadows:

- There's no special keying involved.
- You can position digital shadows wherever you want.
- You have more control over the appearance of the shadow.

Cropping and spot masking the source clip

If the image in the input clip extends beyond the edge of the color screen, shows any unwanted objects such as a light stand or boom microphone, or has harsh shadows or wrinkles that can't be keyed out, then you can use a regional mask. This is often referred to as *garbage matting*.

Unlike color keying (chroma keying), which makes certain colors transparent or semitransparent, regional masking makes certain areas of the frame totally transparent regardless of the content's colors.

Ultra provides two methods for applying regional masks. Use the Input Cropping controls on the Input tab to block out areas on the edges of the frame. Use the Mask Painter tool to mask out spots anywhere in the frame.

Both methods leave a sharp edge of transparency that can remain apparent after keying, particularly if the background had any shadows or wrinkles that spanned the masked region. To blur these lines so that they are less obvious, adjust the Edge Softness slider at the bottom of the Input Cropping control set.

Regional masks remain in a fixed position throughout the session. However, the chroma key adjusts dynamically to the movement of the camera and the subject. Preview the full clip to ensure that no masked areas are cut off or holes through the subject are left.


In some sessions, masking can introduce space that makes it look like the subject is appearing from thin air rather than entering the frame from behind a foreground element as intended. To remedy this problem, move the input clip, which eliminates the need to crop the side. For more information, see [“Moving and flipping the input vertically and horizontally” on page 97](#).

Cropping the edge of a frame


The Input Cropping controls on the Input tab provide a quick method for masking off an entire edge of the frame, making the affected area of the input clip fully transparent. To crop an edge, drag the appropriate side of the blue-gray box with the corner and midpoint nodes in the Input Cropping control group. In this control, the black rectangle that's revealed when you crop an edge represents the borders of the source. The Output Preview Monitor instantly reflects this change.

Painting a mask

The Mask Painter lets you cut transparent holes in the input clip wherever you choose.

1. Click the Mask Painter button  below the Input Preview Monitor. If this button is not displayed, then the input clip is not selected.
2. Drag in the Input Preview Monitor across the area that you want to mask out. The pointer appears as a black circle. The Input Preview Monitor and Output Preview Monitor instantly reflect the change. Zooming in the Input Preview Monitor gives you finer control.

Removing a spot mask

If you cut a regional mask that's too large, you can trim it back with the Mask Eraser tool. Activate the Mask Eraser tool , and drag in the Input Preview Monitor to paint an area back to opacity. This tool works only with regions masked using the Mask Painter, not on areas along the edges that were cropped.

NOTE

If you're painting or erasing the input clip after setting the key, the masked area is essentially invisible. To see the painted mask, disable the keyer by selecting Enable on the Keyer tab. This is particularly useful when erasing a mask so that you can see better where you need to erase.

Fine-tuning the Keyer settings

If an input clip has a washed out or inconsistent background color, a tricky subject, or other keying challenges, you must manually change the input clip to get the results you expect. Even some high-quality input clips may require more than clicking the Set Key button to yield a key that is acceptable. This section covers the steps to achieving the absolute best possible results from the video. For more information about the controls on the Keyer tab, see [“Keyer tab” on page 35](#).

Viewing the key

The first step in fine-tuning the keyer settings is to see what the key looks like. Two measures that will help you see the key better are zooming in on a trouble spots and switching to a neutral background. For information on panning and zooming the view in the monitor, see [“Magnifying and repositioning the view in the monitors” on page 33](#).

Switching backgrounds

Switching temporarily to a pure white, pure black, or checkerboard background can help you detect and eliminate imperfections in the key. For your convenience, these useful backgrounds are built into the Background layer thumbnail. Right-click the Background layer thumbnail, and try the different options to see which one best reveals various problems. In general, black and white work help you check the key along the edges and isolate imperfections in the input clip’s background, and the checkerboard backdrop helps you detect an unwanted transparency.

To change back to the desired background when you’re finished changing the keyer settings, right-click the Background thumbnail, and choose Reassign Last Source to retrieve the original image.

NOTE

For most keyed scenes, a pure white or black test background represents the most challenging possible keying situation. You can use these backgrounds to tune the key more precisely than you can with an actual background. However, trying to eliminate all of the shading or noise in the video can be a frustrating and impossible challenge and can actually yield less appealing results than leaving the key a bit less than perfect. This is because achieving a perfect key can require extreme settings that reduce the quality of the overall appearance. For example, removing the last hint of green in the subject’s hair can result in a loss of definition along the edges.

When viewed against a real-world background, minor flaws in the key are usually not visible. Therefore, Adobe recommends that you use the white and black test backgrounds only for broad changes, and then use the actual background over which the clip will be composited to fine-tune the settings. If you later change the background, you may need to readjust the key.

Basic keying workflows

This section suggests a sequence of steps to fine-tune a key. The order of the steps is important because various settings on the Keyer tab interact with one another. Proceeding in a different order may result in taking one step forward in one regard, only to find that you’ve moved back two steps in another regard.

Keep in mind that each step in the process moves you closer to the goal of a convincing key, so don't try to accomplish too much with any given adjustment. After performing these steps a few times, you'll learn how the later steps build on the earlier ones. This sense of the whole process will serve you well in developing a feel for how much to change each setting during the process.

This fine-tuning process begins after you use one of the methods discussed in previous sections to set the key. If you're satisfied with the key, then you don't need to proceed with the following steps.

This procedure assumes that the color screen is green, but these steps are the same for a bluescreen.

1. Click the Keyer tab. If the controls are disabled, click the Input Clip layer thumbnail.
2. Move the Transparency and Desaturation sliders all the way to the left (0.000), and move the Spill Suppression slider all the way to the right (1.000).
3. Increase Start Level in the Color Control area until most of the background is keyed out, but a green halo remains around the subject. It's okay if a little green remains elsewhere in the background.



A) Green halo B) Green remnants

4. Increase Desaturation so that all of the remaining green turns magenta, but not so far that the magenta bleeds onto the subject. If you're working with a bluescreen, the blue remnants turn yellow.



A) Halo turned magenta. B) Desaturation went too far; magenta bleeding onto subject.

5. Decrease Spill Suppression until the magenta or yellow highlights are gone, but not so far that any of the green spill returns.
6. Set Start Threshold to the same value as Start Level, and set Transparency to the same value as Desaturation. This should produce a reasonably good overall result.
 - a. If the subject has any transparency in both dark and bright areas, then reduce the Transparency setting.
 - b. If only bright areas of the subject are partially transparent, then increase the Highlights setting.
 - c. If only dark areas remain somewhat transparent, then increase the Shadows setting.
7. If the input clip was captured from an analog source and contains a troublesome green or blue edge around the subject that you cannot eliminate by using the Color Control steps, then adjusting the Sensitivity setting may resolve the issue. This control can also help eliminate any green remaining in dark shadows. Increasing this setting makes the keyer include a wider range of colors, which means that it's less sensitive or selective in what colors are keyed out. Clips that are well lit with a good background should not require any change to this setting. So if you find that you need to change the Sensitivity for many of the clips, then you should work on the setup in the studio to eliminate dark shadows below and behind the subject.
8. If the edges of the subject are jagged, change the Post-Processing controls, particularly the Soften Matte and Sharpen Matte settings. The Soften Matte setting smooths jagged edges, but makes them blurry. The Sharpen Matte setting removes some of the blurriness, leaving a crisper, smoother edge.

You should only change these settings as a last resort. These settings change how Ultra defines the edges of the matte. Although changing these settings can resolve some issues, they also tend to cause subtle parts of the subject, such as hair and transparent objects, to disappear. As with the Sensitivity, Color Curve, and Alpha Curve controls, if you need to change the Post-Processing settings, there may be a problem that you can resolve in future clips by improving the lighting and setup. To learn more about how each slider affects the key, see “[Keyer tab](#)” on page 35. You may also want to check out the keying tutorials available on the Ultra support website: www.adobe.com/support/ultra.

If you are preserving the shadow in the input clip, do not change the Shrink Matte setting, because it weakens the shadow and leaves artifacts.

Saving and applying Keyer settings

You can save a profile of all of the settings on the Keyer tab and apply it to other sessions. You can also use this feature within a given session to preserve a particular set of settings before making changes, and then easily return to them if you don’t like the results of the changes. The profile encompasses only the Keyer slider settings; it does not include the mathematical model that’s created when you click Set Key or Apply Points.

To create a profile, click the Save button in the lower-left corner of the Keyer tab. A standard Windows Save As dialog box appears. The default path is My Documents\Adobe Ultra CS3\My Settings. The profile’s extension is .cks.


To apply an existing profile to the current session, set the key, click the Load button, browse to the correct folder if necessary, and then select the desired profile.

Positioning layers and performing virtual camera moves

This section describes how to move and scale layers and provides instructions for panning and zooming within a session.

Differences between sets of Position controls

The Position controls on the Scene tab are for moving the active layer within the 3D environment. The Position controls on the Input tab are for moving the input source within its two-dimensional layer.



- A) The Position In Scene controls in the Scene tab move the layer within the full frame.
- B) The Input Offset controls in the Input tab position and scale input within the layer plane.

The Position In Scene controls on the Scene tab let you move and scale the layer anywhere within the full frame or beyond the edges of the frame. This set of controls and the Orientation In Scene controls collectively define the size, position, and orientation of the layer plane, or the space within which the layer's input appears. Unlike a plane in broad geometrical terms that extends to infinity in both dimensions, a layer plane in Ultra has defined borders. The Input Offset controls on the Input tab function only to position and scale the image within the borders of the layer plane.

As a rule, you should use the Input Position and Input Orientation controls whenever possible to achieve the desired composition because they provide greater control and they're not hardware-dependent.

To prevent moving images out of their necessary position, these settings are locked for insets in the background of virtual sets and the input clip in VirtualTrak shots. In these cases, correct the layer's position with the Input Offset controls. Because the offset is hardware-dependent, some video cards do not fully support this functionality.

Adjusting the framing

The Position In Scene and Input Offset controls are only two methods for controlling the scale of images or the framing of what's displayed in the Output Preview Monitor. If what you see in the monitor is not what you expect, check the settings described in the following table.

Control	Tab	Description
Position In Scene	Scene	Controls the size and position of the layer plane. See “Changing the position and scale of a layer plane” on page 92 .
Orientation In Scene	Scene	Controls the perspective of the layer plane in all three axes. See “Changing the orientation of a layer plane” on page 93 .
Size In Scene	Scene	Controls the scale of layer plane independent of the Z setting in the Position In Scene controls. You can scale the layer plane of the input clip in sets that lock the other Scene controls. See “Rescaling the input clip’s layer plane in a virtual set” on page 92 .
Input Offset	Input	Controls the size and position of the image on the layer plane. See “Moving and scaling an input within the layer plane: Input Offset controls” on page 95 .
Pan and Zoom	Pan & Zoom	Controls the region of the composited scene that is shown for every frame of the exported clip. See “Panning and zooming” on page 99 .
Pan and Zoom	Output Preview Monitor	Controls the region of the scene that is shown in the monitor. This affects only what you see within Ultra. It has no effect on what’s exported. See “Magnifying and repositioning the view in the monitors” on page 33 .


Setting the size, position, and orientation of a layer plane

The Scene tab contains the controls for changing the size, position, or orientation of a layer. Changing the scale and position of the input clip and other layers is a basic step in the typical workflow for setting up a session. Although you may also change a layer’s perspective during that process, you’re more likely to use the orientation controls when building your own set. For more information, see [“Creating elements for a set or individual layers” on page 68](#). The settings in these two controls collectively define the layer plane, which limits the range of motion possible through the Input Offset control. For more information, see [“Differences between sets of Position controls” on page 89](#). If you’re not familiar with how repositioning a layer with the Position In Scene controls on the Scene tab differs from moving a layer with the Input Offset controls on the Input tab, see [“Positioning layers and performing virtual camera moves” on page 88](#).

The Pause Point Settings control defines the length of a pause in a VirtualTrak shot. For more information, see [“Setting a pause point for a VirtualTrak effect” on page 107](#).

TIP	For fine control of the changes, Alt-drag. This refines the response by a factor of 10.
NOTE	For an input clip in a VirtualTrak set, Ultra locks the controls for changing the size, position, and orientation because the subject’s position is essential to making the input clip work. These controls are also frozen for all of the insets in any virtual set because the alpha regions in the background dictate the position of these subbackground graphics. Use the Size In Scene slider to change the scale of the layer plane for the input clip or any other layer if the subject looks too small or large in relation to the scene.

Changing the position and scale of a layer plane



*A) Y axis - Vertical position: Drag vertically. B) Z axis - Scale: Shift-drag vertically.
C) X axis - Horizontal position: Drag horizontally.*

The Position In Scene control sets the position and the size of the layer. Before repositioning the input clip, find the spot where the current position is most problematic, determine the direction and distance that you need to move the layer, and then drag the preview slider through the segment, looking for places that may be adversely affected by the new location. With insets in a custom virtual set, the correct position and orientation are essentially defined by where you cut the transparent holes in the background. For more information about moving and scaling these layers, see [“Positioning insets in custom virtual sets” on page 94](#).

To move the layer right and left along the x axis, drag the Position grid sideways, or enter a value in the X field.

To move the layer vertically along the y axis, drag up and down, or enter a value in the Y field.

To shrink or enlarge the layer, Shift-drag up or down, or enter a value in the Z field.

The right-click menu for the grid control provides options for resetting values individually or collectively.

Rescaling the input clip's layer plane in a virtual set


Use the Size In Scene slider if a virtual set's predefined layer plane for the input clip is too small to show the subject correctly scaled to the set. This slider is in the lower-left corner of the Scene tab. The Size In Scene slider lets you shrink or enlarge the layer plane for the input clip or whichever layer is selected.

Unlike changing the scale by using the Position In Scene grid control, which works relative to the absolute center of the layer plane, adjusting this slider works relative to the middle of the plane's bottom border. This means that the subject shrinks and grows from the ground up rather than from the center out. Of course, in a wide shot where you can see the subject from head to foot, the position of the subject's feet probably changes to a degree because there's generally some greenscreen below the feet. If necessary, you can counter this upward creep by moving the subject down with the Input Offset control. For more information, see [“Moving and scaling an input within the layer plane: Input Offset controls” on page 95](#).

The Size In Scene slider is not restricted to virtual sets for which the Position In Scene controls are locked. In fact, when working with the virtual sets that you create, you may find this slider preferable to the grid control because it works from the ground up. Adobe recommends that you position the bottom of the layer plane as desired with the grid control, and then change the scale by using the Size In Scene slider

Changing the orientation of a layer plane

The Orientation In Scene control lets you rotate the plane of the image around the three axes. All three values work on a 360° scale ($\pm 180^\circ$).



A) Y axis - Rotate around the vertical axis: Drag sideways. B) Z axis - Spin around the perpendicular axis (angle): Shift-drag vertically. C) X axis - Rotate around the horizontal axis: Drag up and down.

To rotate the layer around a horizontal axis (that is, in the vertical plane), drag the Orientation grid up and down, or enter a value in the X field.

To rotate the layer around the vertical axis (that is, in the horizontal plane), drag sideways, or enter a value in the Y field.

To spin the layer on its center point (that is, rotate around the perpendicular axis), Shift-drag up and down, or enter a value in the Z field.

Dragging sideways in the Position In Scene control changes the X value, but changes the Y value in the Orientation In Scene control.

The right-click menu for the grid control provides options for resetting values individually or collectively and for rotating the plane in 90° increments on the perpendicular axis (Z).

NOTE

The orientation is relative to the center of the 3D space, which for virtual sets is often not the actual center of the frame. For example, you may expect that a Y value of 90° always shows the plane edge-on; however, this is only true if the 3D-center is centered on the frame in the horizontal dimension and the position is centered in that plane. If either the 3D-center or the current position is off-center, then the layer has a dimension with the value set to 90°.

NOTE

Because of the interrelationship of the three coordinates, any given orientation can be defined by two sets of coordinates. As a result, Ultra may under certain circumstances change a set of values to a different set of values with identical results. For example, if all three values are zero and you enter 180 for Y, Ultra displays 180 for X, 0 for Y, and 180 for Z.

Positioning insets in custom virtual sets

All of the custom sets (such as “Simple Keyed with B”) are in the Basic folder of the Virtual Sets library and are initially scaled to full frame. Although in special circumstances you may want to display an inset in full frame, you typically scale and position each inset to its correct location as defined by the transparent regions in the custom background. Adobe recommends the following workflow:

1. Assign the desired basic set and background. If necessary, change the size, scale, and orientation of the background.


You must use a background that has one or more transparent regions cut in it to show the sources behind it. For backgrounds that you use with one or more inset sources, you must create an alpha region in the graphic for each inset.

2. Click the inset’s thumbnail to make it the active layer. If the basic set has multiple insets, then Source B is selected by default.
3. Assign the desired source to the inset.
4. Reduce the scale to roughly the size of the transparent region in the background through which it will be seen. You probably can’t see the image in the Output Preview Monitor, so you must rely on the relative size of the grid in the Position In Scene control.
5. Change the position so that the image is centered in its transparent region.
6. Fine-tune the scale, orientation, and position to achieve the desired framing.

7. If the basic set has another inset layer, then select it through the list above the inset's thumbnail and repeat steps 3 through 7 for that layer.

Moving and scaling an input within the layer plane: Input Offset controls


If you're not familiar with how moving a layer with the Input Offset controls on the Input tab differs from repositioning a layer by using the Input Position In Scene controls on the Scene tab, see [“Positioning layers and performing virtual camera moves” on page 88](#).



A) Black box represents the borders of the layer plane. Content outside this box is cropped. B) Y axis - Vertical position: Drag up and down. C) Angle: Ctrl-drag vertically. D) Scale: Shift-drag vertically. E) X axis - Horizontal position: Drag sideways.

Use the Input Offset controls, which are at the center of the Input tab, to move and scale the active layer within its layer plane. For more information, see [“Differences between sets of Position controls” on page 89](#). In general, you should use these controls only when the Input Position In Scene controls on the Scene tab are locked for the layer, which they are for the input clip in a VirtualTrak set and for all insets (Source B, C, and so on) in all virtual sets.

The black box in the Input Offset grid control represents the layer plane. It does not change to reflect the size or orientation that is set by using the controls on the Scene tab. If you change the Input Offset so that any part of the image lies beyond the black box (see the pink areas in the previous graphic), that part is cropped from the image. Conversely, any places where the edge of the grid is within the layer plane (see the checkerboard areas in the previous graphic) appear either transparent or black, depending on the set. The following graphic shows what would be displayed with the Input Offset settings from the previous example.



Given how these controls function within the layer plane, these controls are useful in the following situations:

Repositioning an input clip in a VirtualTrak scene. VirtualTrak sets lock the Input Position In Scene controls that you usually use for this purpose. These controls are particularly valuable in this regard if the input clip is a few pixels off so that the subject appears from the middle of space rather than emerging from behind a door, pillar, or other foreground element.

Zooming in on a part of the image by increasing the scale of the source and, if necessary, repositioning it for the desired framing.

NOTE

The Input Offset controls require hardware capabilities that not all video cards support. For those video cards, you may see artifacts around an image when it does not fill the layer plane. In some cases, cropping the edges slightly with the Input Cropping tool can delete the visible repeat. For more information, see [“Cropping the edge of a frame” on page 84](#).

NOTE

Vertical, horizontal, and angular movement is relative to the native coordinates of the source. If you rotate the source or flip it in either dimension by using the position and orientation controls on the Scene tab, then the image’s motion seems contrary to the mouse’s movement.

TIP

If you're working with a keyed input clip and want to see the size, position, and orientation of the input clip within the frame, try either disabling the keyer or switching to a solid image. The easiest way to do this is to right-click the Input Clip thumbnail, and then choose Assign White, Assign Black, or Assign Checkerboard. When you're ready to see the keyed video against the background again, right-click the Input Clip thumbnail, and then choose Reassign Last Source.

Moving and flipping the input vertically and horizontally

To move the input horizontally along the X axis, drag the Input Offset grid sideways, or enter a value in the X field.

To move the input vertically along the Y axis, drag the grid up and down, or enter a value in the Y field.

To flip an image so that subject who was looking to the left is now looking right, or vice versa, select Flip Horizontal below the grid control

To flip an image so that the top becomes the bottom, select Flip Vertical.

Rotating the input

To rotate the input around its center point, Ctrl-drag the Input Offset grid vertically, or enter a value in the Angle field. The scale for this field is 360° ($\pm 180^\circ$).

Turning the image 90° to display it in the portrait orientation

To rotate an image so that it is displayed in the portrait orientation rather than landscape, select Plus-90 (Portrait) below the grid control. This turns the layer 90° counterclockwise. If this leaves the image upside down, then select Flip Horizontal. Even though you're correcting how the image is displayed vertically in the frame, you use Flip Horizontal rather than Flip Vertical because these controls work relative to the image's native orientation.

TIP

By turning a standard-definition clip sideways, you can use footage from a standard-definition camera in a high-definition scene. What distinguishes HD from SD is the number of horizontal lines (scan lines, or rows of pixels) in the image. Since SD NTSC video is 720x480 in its regular landscape orientation, rotating the video to portrait mode produces 720 lines of resolution.

To create footage for use in an HD scene with an SD camera:

1. Shoot the input clips with the SD camera turned sideways.
2. Assign the resulting 720x480 clip to a 16:9 virtual set with a background that has at least 1280x720 resolution.
3. Enable the Plus-90 mode. This rotates the input clip 90°. If Scale To Fit is enabled—which it is by default for the input clip—then the image also automatically shrinks so that it fits in the vertical dimension of the set. You can change the scale and position if necessary to achieve the desired composition.
4. When everything else about session is set as desired, save the output movie with the resolution set to 1280x720.

The advantage of shooting with an HD camera versus an SD camera turned on its side is that you have room for the subject to move around. But you also have something to gain by turning the camera sideways—1920 lines of video instead of 1280. If you zoom in on HD video in its normal landscape orientation, you will soon run into pixelation as the zoom ratio exceeds the 720 or 1080 lines. With the camera turned on its side, you can shoot footage that you can then zoom in on much more in Ultra without pixelation problems.

Changing the scale of the input

To shrink or enlarge the input, Shift-drag the Input Offset grid vertically, or enter a value in the Scale field.

Scaling an input source to fit the virtual set

If the aspect ratio of a source image or video does not match the aspect ratio for a session (4:3 or 16:9, which is set by using the Output tab), then by default Ultra zooms to the center of the image so that it fills the frame, cropping either the sides or the top and bottom.

To scale the source so that the full image is displayed within the Output Preview Monitor, select Scale To Fit.

TIP

For fine control of changes to these grid controls, Alt-drag. This refines the response by a factor of 10.

NOTE

The right-click menu for the Input Offset grid control provides options for resetting values individually or collectively and performing common rotations, flips, and zooms.

Returning all grid settings to the defaults

Clicking the Reset button returns all of the Input Offset values to the default settings. This action does not affect check boxes in this control group, such as Scale To Fit and Portrait.

Panning and zooming

Ultra lets you program complex virtual camera movements into a session to produce pans and zooms and also tilts, dolly shots, and boom maneuvers. If you've ever tried to capture such shots on film or tape, you know how tricky they can be. A take can be ruined by the slightest jiggle, and it sometimes seems impossible to maintain focus and framing through a camera move of any complexity. Ultra delivers the desired results with no such glitches and with precision down to the frame and the pixel.

You can program up to 64 pan and zoom points—though you may be better off editing simple scenes together with an NLE than designing a scene that's this complex.

Each virtual camera move follows a straight line from one pan and zoom point to the next. If you want a movement to follow an arc, set multiple points that collectively form a curved path. The speed of a move is a function of the distance between the two points divided by the time between them. To make the moves smoother and more natural, the rate accelerates at the beginning and decelerates at the end. Adobe uses a Hermite spline to calculate the rate curve.

NOTE

Ultra's support for high-resolution graphics and HD video and its pan and zoom capacity lets you create some truly stunning results. Because Ultra maintains the resolution of still images up to 4096x4096 rather than automatically converting all graphics larger than 720x480 to that resolution, all of those pixels are still there. (The maximum resolution for still graphics may be less, depending on the limitations of the graphics card.) When you zoom in and then zoom in further on a high-resolution image, the image remains crisp and unmarred by the blockiness or fuzziness that comes from enlarging low-resolution graphics.

TIP

When making spatial adjustments, you should start on the Scene tab if the virtual set permits changes there, and then proceed to the Input tab if necessary to finish with the Pan & Zoom settings. This is because the position of all of the layers and their sources must be finalized before programming the pan and zoom points.

Grid control

The grid control on the Pan & Zoom tab sets the scale and position of each pan and zoom point. The following explains what the grid control displays and how it works.

Visible frame: The black rectangle around the edge represents the visible frame, or the area that will be exported. This area remains stationary when you move the grid. The shape of this area is controlled by the setting for the aspect ratio of the session on the Output tab.

Scene: The blue-gray 4 x 4 grid represents the composited scene. The aspect ratio of the grid corresponds to the aspect ratio of the current set. The size and position of the grid change when you drag it or enter values in the X, Y, and Z fields.

The perimeter of the grid reliably represents the boundaries of the scene only if the following occur:

You're using a virtual set from a Master Sets Library or the background for the Basic set is the same aspect ratio as the session


The scale of the background is set to 0.000 (1:1) on the Scene tab.

No other layers extend beyond edges of the background.

However, if you use the Scene tab to enlarge the scale of the background or another layer or if other layers are distributed beyond the background, then by definition there is content outside the grid. In that case, the grid display loses any meaningful context, so you must rely entirely on what's shown in the Output Preview Monitor. The bottom line is that you can set pan and zoom points where the grid is entirely out of view in this control. If there's content there, then it's visible. If there's no content there, then all you see is solid black.

NOTE

To avoid breaking the context of the Pan & Zoom grid control, Adobe recommends that you do not increase the scale of a layer plane by using the Scene tab beyond the size of the visible frame unless there's a good reason to do so. For example, you may want to enlarge a 4:3 image to fill a 16:9 frame or zoom in further during a virtual camera move than is possible with the layer plane's scale at 1:1.



A) Black box represents the borders of the publishing frame. Content beyond the box is cropped; area inside the box but beyond the grid may be blank. B) Y axis - Vertical position: Drag up and down. C) Z axis - Scale: Shift-drag vertically. D) X axis - Horizontal position: Drag sideways.


To pan right and left along the X axis, drag the grid sideways, or enter a value in the X field.

To pan up and down (that is, tilt the Y axis), drag up and down, or enter a value in the Y field.

To zoom in and out, Shift-drag up and down, or enter a value in the Z field. You cannot zoom out any farther than 1:1 (0.000).

The right-click menu for the grid control provides options for resetting values individually or collectively.

Adding and setting a pan and zoom point

1. Reset the Output Preview Monitor to full frame view by clicking the  button. Even if you're certain that it already shows the full frame, it's worth taking the time to click the button before setting any pan and zoom points. If the monitor is zoomed in when you set points, the final results may not be what you expect.
2. Enable panning and zooming by selecting Enable in the Pan & Zoom tab. When you first enable panning and zooming, two points are set by default—one in the first frame and the other point in the last frame.
3. Drag the preview slider to the frame where you want to set a pan and zoom point.

For sessions that don't contain video clips, you must set a duration for the input clip before you can preview the session and add pan and zoom points. Enter a time in the Out Point field on the Input tab. If you're not certain exactly how long the session will be with the virtual camera moves, set a value higher than you expect to use, and then correct it after you program all of the camera moves.

4. Click the Add New Point button. A new entry is inserted in the appropriate order in the list of pan and zoom points.
5. Change the scale and position with the grid control. The Output Preview Monitor shows the pan and zoom position.
6. Repeat steps 3 through 5 for each additional point. To delete a pan and zoom point, select it in the list, and then click the Delete Current Point button.

NOTE

If the first, last, or both pan and zoom points are set to the session's first and last frames, respectively, and you change the total length of the session, then the times for those points automatically change. The time setting for intermediate pan and zoom points, however, do not change if, for example, you trim the In point of the input clip after programming virtual camera moves. Therefore, Adobe recommends that you get the session's timing settled before designing pan and zoom maneuvers.

NOTE

The Output Preview Monitor always shows the visible area for the current frame in the session. This means that if you drag the preview slider away from the frame for the currently selected pan and zoom point and then change the zoom and position settings, the monitor does not represent the new framing. You may see a change in the framing for the current timepoint, but that's because changing a pan and zoom point affects the visible area for all of the frames between that point and the one on either side. To have the Output Preview Monitor show exactly where a pan and zoom point is, the current frame must precisely match the current pan and zoom point. To jump to that frame, deselect and reselect the current point.

Changing a pan and zoom point

To change the setting for an existing pan and zoom point, click its row in the list in the Pan & Zoom tab. The position and zoom settings change dynamically as you move the grid control or manually change the values in the X, Y, and Z fields. However, the time setting does not change dynamically when you select a point and preview the session, but rather requires a discrete step, either clicking the Set to Preview Time button, or typing a framecount in the Time field and pressing Enter.

Programming a continuous virtual move with multiple points

To produce a continuous move that zigs and zags, follows an arc, or changes zoom direction rather than going straight from point A to point B, add a sequence of pan and zoom points, one at each position where you want the pan or zoom direction to change. The rate of movement is a function of distance over time. It is graduated at the start and end of each leg.

Programming multiple moves with pauses

To have the framing hold steady for a period of time between two moves, you must set two pan and zoom points for the same position. This type of sequence would look similar to the following:

Time A / Position 1

Time B / Position 2

Time C / Position 2

Time D / Position 3

The difference between Time B and Time C is how long the position remains unchanged.

Panning and zoom with different aspect ratios

If the frame aspect ratio for the session is 16:9 and the frame aspect ratio of the set is 4:3, then the correct Z setting to zoom in just enough to fill the frame laterally is -0.333. At this setting, you can change the Y value from 0.333 to -0.333 without any empty lines appearing at the top or bottom of the visible frame.

If the aspect ratio for the session is 4:3 and the aspect ratio for the set is 16:9, no such change is necessary because the vertical dimension of the scene is already scaled to fit the visible frame, and the sides of the scene extend beyond the edge of the frame.

These values assume that the scale of the layer plane is 1:1.

Viewing a session without virtual camera moves

If you programmed pan and zoom points, but want to view the session without panning and zooming, disable the feature by deselecting Enable.

Achieving the correct timing for video clips

This section describes the tasks involved in achieving the correct timing of video clips.

Trimming the In and Out Points in a video clip

If a video clip contains any content at the beginning or end that you don't want to include in the current session, you can trim the unwanted frames using the In Point or Out Point control on the Input tab. If the input clip has reference frames for keying purposes, this is how you can prevent them from showing in the output movie. You can also use these controls to cut a particular source clip into segments for a series of sessions that collectively produce an advanced compositing result in which the subject appears to be behind a graphical element at one point and in front of it at another point.

The Input Preview Monitor shows the entire length of the source clip, but the Output Preview Monitor shows only the trimmed clip.

The In Point and Out Point settings are reset when you assign a different clip to the layer. If you intend to return to the original trimmed clip and want to reapply the same trim points, make sure that you note the timecodes before switching sources.

The In and Out points do not affect the source clip. They are the timepoints where Ultra starts and stops playing the clip in the session.

For more information, see [“Advanced compositing tasks” on page 72](#). For video clips that are assigned to a layer other than the input clip and are longer than it, you should trim them so that they end at the same time as the input clip.

The steps are the same regardless of whether you're trimming the In Point or the Out Point.

1. In the Input Preview Monitor or Output Preview Monitor, drag the preview slider to show the frame that you want to trim.
2. To trim the content before the current position, click the Set button to the right of the In Point timecode field. To trim the content after the current position, click Set for the Out Point field. The time displayed at the lower left of the Input Preview Monitor is set as the timecode for the selected trim point, and the Trimmed Duration reading to the right of the trim point controls indicates the length of the clip based on the current settings.

NOTE

To return the In Point setting to zero or the Out Point setting to the end of the clip, click the Reset button for the appropriate control.

NOTE

If you know the desired timecode, you can also type it directly into the field. In this case, do not click the Set button because it applies the current time.

NOTE

The trim controls are locked when the active layer is the background for a VirtualTrak set, which is a special type of animated clip.

Looping the clip

You can set a video clip assigned to any layer to play in a loop for as long as the session runs. By default, all of the layers except the input clip are set to loop.

1. If the layer to which the video clip is assigned is not already the active layer, click its thumbnail to activate it.
2. Select Loop Source on the Input tab.

NOTE

For a looped source to appear reasonably natural, the beginning and end must be such that the viewer will not notice when the clip restarts. If trimming the start or end point will help achieve this result, then the In Point and Out Point controls may be of use.

NOTE

You will rarely, if ever, want to loop the input clip, because it's normally the longest source in the session. If you do encounter a situation where you want to loop the input clip, this option is also available for that layer. Looping the input clip will create an infinite loop. Ultra sets the end of a session by the longest nonlooping source to avoid an endless cycle.

Specifying when a video clip begins playing in the session

The Offset Into Scene setting delays the start of a video clip by the specified time after the beginning of the session. Although you can delay the start time for any video clip in any layer of any type of virtual set, you will usually want to do this only in a session that uses a VirtualTrak effect. Achieving the correct timing for three points in the video is the most important task in setting up a VirtualTrak clip. Most VirtualTrak effects open with a virtual camera movement that takes several seconds to track, pan, or zoom to the plane where the input clip is displayed. You typically want to wait at least until the Virtual Trak effect brings that plane before having the input clip begin playing, and you may prefer to delay its start until the effect ends.

These instructions refer specifically to setting the Offset Into Scene time for a VirtualTrak effect, but the steps are essentially the same regardless of which layer a clip is on or what type of virtual set is assigned.

1. Create a session with a virtual set that has a VirtualTrak set and an input clip in which the subject walks into frame.

The name of a VirtualTrak set is followed by “(Trak)”. An example of a VirtualTrak set is the “Museum Intro (Trak)” set in the Virtual Sets\Museum library (from MSL1).

If you don’t have your own input clip handy, use “Suzy – Wide – Walk in Left”, which is in C:\Program Files\Adobe\Adobe Ultra CS3\Content\Sample Clips\NTSC Sample Clips.

2. In the Output Preview Monitor, drag the preview slider to the time when you want the clip to begin playing. For VirtualTrak effects, this is typically when the plane of the input clip appears or at some time shortly thereafter. If you’ve already keyed the input clip, disable the keyer so that you can see the plane appear.
3. Click the Set button for the Offset Into Scene setting on the Input tab. This applies the current framecount from the Output Preview Monitor to this field, delaying the playback of the input clip until this point in the session.
4. Reenable the keyer and play the session in the Output Preview Monitor again to assess the timing of the subject’s appearance. If the timing isn’t correct, then you probably need to trim the In point for the input clip as described in [“Trimming the In and Out Points in a video clip” on page 104](#). For example, in the “Suzy – Wide – Walk in Left” clip, the subject doesn’t enter from the left until frame 17.
5. If the subject’s position isn’t correct relative to the virtual set, then you must change the position of the input. For more information, see [“Moving and scaling an input within the layer plane: Input Offset controls” on page 95](#).

NOTE

If you want to try adjusting the timing for a VirtualTrak session using a clip that’s built into Ultra, see the tutorial titled “Adjusting Timing on a VirtualTrak set shot” at www.adobe.com/support/ultra.

Setting a pause point for a VirtualTrak effect

Some VirtualTrak sets let you pause the effect so that the virtual camera move allows time for a video clip to play, subject to talk, or credits to roll. For example, in the “Library Book to Talent with Pause” set in the Master Sets Library 1 (MSL1), the camera starts with a tight shot on a book containing an inset Source B. If you insert a video in the Source B, you must program a pause time so that the camera waits the appropriate length of time before beginning the virtual pan to the location of the input clip. You may want to enter a pause time for a still image as well if you want the audience to have time to study it.

Ultra defines the Pause Begins At time; you specify the Pause Ends At time. Typically, it takes the following steps to accomplish this:

1. Select the correct Input Source.
2. In the Input Preview Monitor, drag the preview slider to the point where you want the virtual camera move to start or resume.
3. Click the Set button in the Pause Point Setting control area on the Scene tab. This applies the time from the Output Preview Monitor.

Adjusting the volume of a video clip

For any video clip that has an audio track, you can control the volume by selecting the correct layer and adjusting the Volume slider on the Input tab. This is particularly useful for eliminating ambient audio from a clip that you use as the source for any layer other than the input clip.

To mute the audio, move the slider all of the way to the left.

This setting affects the volume in the final output file and what you hear in Ultra.

Fine-tuning the appearance of the video

This section covers a variety of refinements that you can make in Ultra to put the finishing touches on a composited shot. These changes can make the difference between a scene that is merely effective and one that is truly convincing.

The following are changes you can make outside of Ultra to modify your video:

Matching mixed media: If the input clips are DV that were compressed, but the background was shot on film, the two sources may not match perfectly. Typically, the film footage looks too clean compared to the subject. Since there's no way to make the DV clip as clean as the film, you can compress the film clip in an NLE, such as Premiere Pro, using the same codec, or you can add noise using Adobe Premiere Pro.

Matching the audio to the virtual environment: In some situations, you may want to process the audio for a composited scene to make it sound like it was recorded in an environment similar to the virtual set in which the scene takes place. For example, if a scene is set in a large virtual cathedral, you may want to add some reverb to the actor's voice. You can also change the reverb and equalizer settings to simulate relative microphone distance between tight shots and wide shots. You may also want to mix in subtle appropriate ambient sound effects, such as street noise or wind in the trees. You cannot change the audio in Ultra. You can use an application such as Adobe Audition or Soundbooth.

Correcting colors

Ultra lets you adjust the colors of any source in a session. For the input clip, you can make separate adjustments for pre-processing and post-processing. Changes made in the Pre-Processing mode are applied to the source before being keyed and, therefore, affect what the keyer sees and has to work with. Post-Processing adjustments are applied after keying. If the color of the background is not well-saturated and, therefore, is not keying well, then you may want to change them in the Pre-Processing mode. If the keyed subject does not fit in well with the selected virtual set or requires corrections to counter pre-processing color adjustments, then you may want to adjust its colors in the Post-Processing mode. To select the appropriate mode, select its option at the top of the control area. The controls in these modes are identical with the exception of the Gamma slider, which is available only in the Post-Processing mode.

For the other layers, Ultra does not perform processing like keying, so the pre-processing and post-processing distinction is irrelevant. You can change the colors of layers in a virtual set like any other source. For example, if you don't like the Digital Studio sets in blue, you can use the Hue control to change the color. To access those layers, press Alt+P or choose View > Displayed Inputs > Pre-Defined.

NOTE

One of the main reasons you would change the colors is to give the various layers a comparable look and feel. You typically achieve the best results by making moderate changes to two or more sources rather than making more extensive changes to only one source. Keep in mind that achieving a good match between the keyed subject and other layers starts when you shoot the video for the input clip or design a custom set for it, whichever comes later. If you do a good job at that stage in the process, you need only minor color corrections in Ultra.

Making color corrections

By default, the controls on the Colors tab are disabled. Before you can make any changes, you must select Enable to activate the controls. For input clips, you enable and disable the Pre-Processing and Post-Processing controls independently. If you already changed a layer and want to see it in its original state, deselect Enable to disable the controls. All of the current settings are preserved.

The controls on the left side of the Colors tab—Brightness, Contrast, Saturation, and Hue—are common to nearly all video and graphics editing applications.

Brightness: Brightness is the dimension of a color that represents its similarity to one of a series of achromatic colors ranging from very dim (dark) to very bright (dazzling).

Contrast: This control affects the tonal variations between the highlights, middle tones and shadows of the image. Contrast is the difference in visual properties that makes an object (or its representation in an image) distinguishable from other objects and the background.

Saturation: This control affects the intensity of a specific hue. It is based on the color's purity; a highly saturated hue has a vivid, intense color, while a less saturated hue appears more muted and grey.

Hue: This control affects the color type (such as red, blue, or yellow).

The controls on the right side of the Colors tab—Level, Offset, and Gamma—can apply to all color channels or to only one channel. When working with any of these controls, you must first select the color channel that you want to change. By default, the whole spectrum is selected (RGB). To select a channel, deselect the RGB check box, and then select the desired channel.

Level: This control affects only pixels that have a value in the selected color channel. If, for example, you're working in the red channel, pixels that have a red value are less red if you decrease the level and more red if you increase the level. If you're working in the RGB mode rather than having a single channel selected, then the result is the same as the Brightness control because all three channels are adjusted together.

Offset: This slider boosts or cuts the value in the current channel regardless of whether a pixel had any of that color to begin with. If you select the red channel and push this value all the way up, pixels that were pure green (0/255/0) become pure yellow (255/255/0).

Gamma: The result of this control varies depending on the initial value in the selected channel. The results are most pronounced for values at the middle of the 0 to 255 range, and diminish for pixels at the extremes in the selected channel. At the absolute extremes, 0 and 255, there are no changes at all. If a pixel started at chartreuse (127/255/0) and you change the red channel, the color changes noticeably toward a more pure green if you decrease the gamma and toward yellow if you increase the gamma. If you select the green or blue channel, then the pixel is not affected at all. Adjusting Gamma is similar to using the midpoint slider of the Levels control in Adobe Photoshop.

As you adjust a color slider, the results are reflected in the Input Preview Monitor and Output Preview Monitor and in the reference display to the right end of the Colors tab. Ultra provides a selection of color wheels and color bars, each of which provides a different view of the color spectrum and how changes affect its display. To change which one is shown in the reference display, select from the list above the reference display.

Saving and applying color settings

Ultra lets you save a profile of particular color settings and apply it to other sessions. You can also use this feature within a given session to save one or more profiles and switch between them to see which profile you prefer. Each profile saves the settings from the Pre-Processing and Post-Processing modes on the Colors tab.

To create a profile, click the Save button at the lower left of the Colors tab. A standard Windows Save As dialog box appears. The default path is My Documents\Adobe Ultra CS3\My Settings. The profile's extension is .ccs.

To apply an existing profile to the current session, click the Load button, browse to the correct folder if necessary, and select the desired profile.

Adding shadows and reflections

When done correctly, shadows and reflections provide a key finishing touch that helps sell the illusion, melding the subject into the scene. When absent or done poorly, they can destroy the compositing result. Ultra lets you generate up to three virtual shadows and a single reflection on the floor and two shadows on the wall. In addition, Ultra provides the power to change their position and appearance so that they're always done correctly.


Creating realistic virtual shadows is not only in general much easier than trying to preserve the input clip's actual shadows, but also can produce better results. For more information, see [“Keeping the shadow in an input clip” on page 82](#). In addition, if keeping the real shadow is the only reason for using the Apply Points keying method, then choosing virtual shadows also frees you to use the more advanced and effective Set Key method. For more information, see [“Multiple Key Points Method \(Color Spread\)” on page 80](#) and [“Set Key” on page 78](#).

Enabling a shadow or reflection and making it the active one

To turn each shadow or reflection on and off independently, select its check box.


Because a single set of controls on the Shadows tab serves both effects, a particular shadow or reflection must be both enabled and selected as the active one before you can change it. If the desired effect is disabled, then enabling it also makes it the active one. If it's already enabled, then you must click its name in the right column to select it as the active one. Selecting the check box for an effect that's already enabled selects it as the active one, but turns it off in the process. If the sliders are dimmed, then the active effect is disabled.

In the following example, Shadow 1 and Shadow 3 are enabled, and Shadow 1 is active.



Changing the position of a floor shadow


There are four controls involved in setting the position of a shadow. The following diagram shows the result of all of the controls. Although the process looks complex, when you take it step by step, the process is simple enough that you can probably learn how to position a shadow by loading one of the sample sessions and experimenting with the sliders.



A) Spread B) Length C) Angle D) Baseline

To position shadows and reflections

1. Use the Baseline slider to align the bottom of the shadow or reflection with the bottom of the subject. Adjusting this slider moves the horizontal plane on which the shadow lies (the red arrow in the following diagram).




A) Baseline slider bar - Top setting B) Baseline slider bar - Bottom setting C) Red arrow indicates the baseline

Tip

If you're having difficulty aligning the bottom as precisely as you'd like, try changing the Y value for the Orientation In Scene control on the Scene tab to 89° so that the layer plane and the shadow plane are nearly edge-on to you. When the horizontal position is correct, the bottom of the subject and the end of the shadow meet along a line; there is no gap or overlap.


2. Use the Flip Vertically option to specify if the shadow appears behind the subject or in front of it. With classic three-point lighting, the shadow from the back light shows in front of the subject.

3. Adjust the Angle slider to set the direction that the shadow extends from the subject. This corresponds to the angle between the line from the camera to the subject (the black line in the following diagram) and the angle from the light stand to the subject (the green line in the following diagram). Changing this setting is similar to moving the virtual light stand on an arc (the cyan line in the following diagram).




A) Angle slider bar - Left setting B) Angle slider bar - Right setting C) Angle D) Arc

4. Adjust the Length slider to change the length of the shadow. This has the same result as raising or lowering the virtual light on its stand.



A) Length slider bar - High light, short shadow setting B) Length slider bar - Low light, long shadow setting C) Length


5. Adjust the Spread slider to change the width of the shadow relative to the size of the source. This has the same result as moving the light closer or farther away along its current line (the yellow line in the following diagram), which in the real world involves moving the light stand closer or farther and adjusting its height (the orange line in the following diagram).



A) Spread

TIP

When deciding how many shadows to use and where they should fall, try to mimic the position of lights for the shoot. Ideally, you should design the lighting at the shoot with the virtual set in mind. The following graphic represents the types of shadows that you may expect from basic three-point lighting. Notice that the key light shadow is darker (that is, more opaque) than the other shadows.



A) Key light shadow B) Fill light shadow C) Back light shadow

NOTE

Subtlety is crucial when adding virtual shadows. When done well, they should be such an integral part of the scene that the viewer scarcely notices them. In other words, if a shadow or reflection draws your eye, then it may be overdone.

NOTE

The controls for changing the position of a shadow or reflection work relative to the layer plane. Therefore, in some circumstances, the response may be the opposite of what you would assume. For example, if you flip the layer plane by using the Orientation In Scene control, then shadows appear in front of the subject, and the reflection extends behind it.

NOTE

The three floor shadows have different default positions, as described by their names. Shadow 1 - Floor Left and Shadow 3 - Floor Right are designed to produce long shadows cast off behind the subject and off to the sides. Although you can move the shadows to exactly the same positions, Adobe recommends that you keep them in their native sectors if for no other reason than to know which shadow is which when you return to these controls later. Shadow 2 - Floor Center is designed to pool around the subject's feet as if from one or more overhead lights. It is blurrier and more amorphous by design, and the result of the Falloff control differs from the other two shadows.

Changing the position of a wall shadow

When you select a wall shadow, a grid control replaces the set of positional sliders used for floor shadows. The grid control lets you adjust the shadow's position and size. The black rectangle represents the edges of the scene's visible frame.

To move the shadow right and left along the X axis, drag the grid sideways, or enter a value in the X field.

To move the shadow vertically along the Y axis, drag up and down, or enter a value in the Y field.

To shrink or enlarge the shadow, Shift-drag up or down, or enter a value in the Z field.

Enlarging a wall shadow is similar to increasing the spread of a floor shadow in that both effects mimic having a light source close to the subject. Shrinking a wall shadow simulates increasing the distance between the subject and the wall.


Changing the appearance of a shadow or reflection

Four controls affect the appearance of a shadow or reflection. Three controls—Opacity, Falloff, and Falloff Edge—relate to the opacity and how much of the effect is visible. Blur controls how sharp the edges are.

Opacity, Falloff, and Falloff Edge


These controls interact with one another. You generally achieve the best results by changing them in the following order.

1. Opacity controls how transparent the shadow or reflection is across its entire extent. As opacity increases, the color of the shadow shifts toward black.



A) Opacity slider bar - Transparent setting B) Opacity slider bar - Opaque setting


2. Falloff applies a gradient of transparency. The shadow or reflection becomes more transparent with distance from the subject. To be more precise, this slider controls how far up the shadow the gradient is applied. Beyond a point, which varies depending on other settings and the nature of the background, the end of the shadow or reflection fades into invisibility. As this value approaches its maximum setting (1.000), the part of the effect that remains visible becomes shorter.



A) Falloff slider bar - No fall off B) Falloff slider bar - Full fall off

3. Falloff Edge stretches and compresses the Fall Off gradient. Stretching the gradient lengthens the distance over which the shadow or reflection drops from the baseline opacity (as set by the Opacity control) to full transparency. If the Fall Off setting made the end of the effect invisible, it may make the entire shadow visible again. Compressing the gradient shortens that distance over which the shadow or reflection becomes transparent. If the slider is all the way to the left, the falloff becomes a crisp line instead of a gradient, which you can use to make a shadow or reflection appear to end abruptly when it reaches an object in the background or foreground.

If the Falloff slider is set to either extreme (0.000 or 1.000), then the Edge Softness control has no impact.



A) Blur slider bar - Sharp setting B) Blur slider bar - Fuzzy setting

Blur

The Blur slider controls how crisp the edges of the shadow or reflection are.

Saving and applying settings for a shadow or reflection

Ultra lets you save a profile of the settings for a single shadow or reflection and apply it to other sessions. You can also use this feature in a session to save one or more profiles and switch between them to see which you prefer.

To create a profile

1. Select the shadow or reflection for which you want to save a profile.
2. Click the Save button in the lower-left corner of the Shadows tab. A standard Windows Save As dialog box appears.
3. Change the path by using the Save In field, if desired. The default path is My Documents/Adobe Ultra CS3/My Settings.

4. Enter a name in the File Name field. The profile's extension is .shw.

To apply an existing profile, select the desired shadow or reflection and then click the Load button, browse to the correct folder if necessary, and select the desired profile.

Defocusing a source

The depth of field, or crispness of focus, in different layers of a composited image can make a difference in how realistic the image looks and subtly cue the viewers as to what's most important in the image. You can digitally defocus any layer in a session by selecting it to make it the active layer, and adjusting the Defocus slider on the Input tab.

This adjustment calls for a light touch. In the following example, the background of the image on the left is in crisp focus. The background of the image on the right has the Defocus set to 0.07, which is just enough to make the umbrella, beach chair, and waves slightly fuzzy, thereby accentuating the distance behind the subject.



Saving the finished video

Ultra provides several options for exporting the composited output of a session for use in nonlinear editors (NLEs) and other graphics and video applications. You can produce videos in HD and SD, you can output in 16:9 and 4:3 frame aspect ratios, and you can save out as a series of still images or video. In addition, you have several frame rates to choose from, with both progressive and interlaced options. Ultra is compatible with applications such as After Effects® and Adobe® Premiere® Pro, as well as other popular video editing software.

Although you often compress your video for distribution when it's finished, you should avoid uncompressing and recompressing clips as you work with them at different stages in the post-production process, because each cycle degrades the quality of the audio and video. If you are working with a movie output from Ultra in an NLE or another application, Adobe recommends that you save the output movies uncompressed. This yields the highest quality video, but also the largest files. However, you'll compress the finished product at a later time. To save uncompressed clips, set the format to DirectShow and set the codec to Uncompressed. Buttons for saving as a 24-bit or a 32-bit keyed source then appear below the codec field. Leave this set to 24-bit.

Lossless compression can and should be used for interchange between Ultra and non-linear editing systems.

TIP

You should generally save output movies in the same resolution that you will use in the editor. One situation that can cause problems is the difference between 720x480 and 720x486. If you use a clip that you export from Ultra at 720x480 in an editor that's set to 720x486, you may have problems because some NLEs incorrectly stretch a 480-line video to fill 486 lines, thereby causing problems with the field order. While that's clearly a problem in the NLE, not Ultra, you can avoid problems by exporting a session to the proper resolution.

To save the finished video

1. On the Output tab, select a format:

DirectShow: DirectShow is a Windows component that supports a wide variety of video codecs. By default, DirectShow supports several common media file formats, such as ASF, MPEG, AVI, MP3, and WAV sound files.

QuickTime: Apple QuickTime is a file format for a container for audio, video, and still-image files. To output to a QuickTime file, you must have QuickTime installed on your computer.

Frame Sequence: This option lets you export a separate still image for each frame in the session. For more information, see [“Outputting still images \(Frame Sequence\)” on page 122](#).

2. Select a codec. The codec options that are available in this list depend on the format that you select and, in the case of DirectShow and QuickTime, on what codecs are installed on the computer.
3. Depending on which codec option you selected, the Configure button may be enabled. If it is, then the codec has parameters that you can customize. See the codec's documentation for more information about the options in its Configuration dialog box.
4. Depending on the codec option, there may be additional options from which you can choose. The following are some of these options:

Uncompressed options: 24-bit (standard) or 32-bit Keyed Source (preserves alpha channel). For more information, see [“Outputting clips or stills with an alpha channel” on page 122](#). If you select 32-bit, then you also have the option to invert the alpha channel for compatibility with applications that interpret alpha channels as film alpha (0 means opacity) instead of video alpha (0 means transparency).

DV Video Encoder: Type 1 (file containing separate streams for audio and video content) or Type 2 (single stream for audio and video). The most common type is Type 2.

With Type 1, the multiplexed Audio-Video is kept in its original multiplexing and saved together into the video section of the AVI file. This method has a relatively small file size, but Windows applications based on the VfW API do not support it.

With Type 2, audio is saved as an additional audio stream into the file. This type is supported by VfW applications, and has a larger file size.

5. Select a resolution. Some codecs lock this option.
6. Select a frame rate. The frame rates that are available vary depending on whether you are working in NTSC mode or in PAL mode.
7. Select a field order that’s compatible with the editing application. If you’re not sure which field should be first, see the NLE’s documentation. Standard-definition video (such as NTSC DV) is typically lower-field first, whereas many high-definition formats (such as DVCPHD 1080i) are upper-field first.
8. Enable the Flicker Filter if the composited scene contains high-contrast thin lines or other patterns that may produce an unpleasant strobing effect in an interlaced video. Clothing with a fine pattern is known to introduce this problem.
9. Enter a name for the output movie in the File Name field.
10. If you want the output movie saved to a path other than the path shown in the Folder field, then click the Browse button, and set the desired path.
11. Click the Save Output button to export the video. The status bar indicates what percentage of the job is finished, and the Time Remaining field estimates how much longer it will take.

NOTE

You may notice that one option on this control panel tab—aspect ratio—is not included in this sequence of steps. That’s because you should have selected 4:3 or 16:9 when you created the session. Changing it at this point may require repositioning layers and reprogramming virtual camera moves.

Outputting still images (Frame Sequence)

Ultra lets you export a session as a series of still images rather than as a video clip. Some advanced image compositing tools work better with this type of frame sequence than with video. This file format also makes the composited content available for use in standard image-editing applications, such as Adobe Photoshop and Fireworks.

To export a series of stills, select Frame Sequence in the Format field, and then select the image type in the Codec field. The frame rate, field order, and resolution also apply despite the fact that you're exporting stills, not video. The product of exporting in this manner is a series of sequentially numbered images, one for each frame. The text that you enter in the Image Prefix Name field appears at the beginning of each image's file name, before the image number. Since a session that is only one minute in length produces well over 1,000 images, you may want to create a folder for each frame sequence that you export. You can do this through the dialog box that appears when you click the Browse button on the Output Folder.

Outputting clips or stills with an alpha channel

If you want to output a clip containing only the input clip with the subject keyed and the rest of the frame transparent, set the format to DirectShow AVI, set the codec to Uncompressed, and then select 32-bit Keyed Source. This option is also available when you export still images (Format = Frame Sequence) as PSD, PNG, BMP, TIFF, and so on.

When you export in 32-bit, only the input clip layer is included, and all of the settings related to the size, position, and orientation, both those predefined by a virtual set or user-defined by using the Scene, Input, and Pan & Zoom tabs are ignored. In other words, 32-bit output movies are 1:1 relative to the source for the input clip layer. If the Input Preview Monitor is 1:1, then what you see is what appears in the output movie.

Troubleshooting and getting help

5

Updating software

A first step in resolving problems with software is often to ensure that you are using the most up-to-date software—for the application, device drivers, and the operating system.

Updating Ultra

If you are having problems with Adobe® Ultra® CS3 and are connected to the Internet, Adobe recommends that you ensure that you are using the most up-to-date version of Ultra software before you try anything else.

To check for updates, choose Help > Updates. Follow the on-screen instructions to check for an update and to download it if one exists.

Even if the update does not fix the problem immediately, it can improve the ability of Adobe technicians to isolate the problem and identify a solution.

Updating device drivers

The hardware devices attached to a computer—such as the mouse, webcam, and sound card—require files called *device drivers* that tell the operating system and other software how to interact with them. Often, hardware manufacturers release new drivers that can increase performance or fix compatibility issues.

If your devices are working with Ultra, Adobe recommends that you do not update them, because sometimes new drivers can cause new problems.

To get the latest drivers for devices connected to a desktop computer, go to the website of the device manufacturer. To get the latest drivers for devices connected to a laptop computer, it is sometimes better to go to the website of the laptop manufacturer.

If your device meets the minimum requirements, then it will probably work with Ultra. If you are having problems, see the Adobe Ultra Technical Support website at www.adobe.com/support/ultra for the most up-to-date information.

Updating the Windows® operating system

In certain situations, you may need to update the Windows operating system.

1. Open Internet Explorer.
2. Select Tools > Windows Update.
3. Follow the on-screen instructions.

Technical Support

Adobe is happy to help you identify and solve any problems that you may have using Ultra software.

You can save time and help us to isolate the cause of the problem by providing complete and accurate information about your computer system. To show a summary of some basic system configuration information, choose Help > About Adobe Ultra. If you are using email or the User Forum to get help, copy and paste this information (except for the copyright information) into your message.

Also, run the DirectX Diagnostic Tool and send the results with the description of your issue.

Technical support web pages

For information on technical support, visit the Ultra support page at www.adobe.com/support/ultra. From the support pages, you can review the latest troubleshooting tips and updates and access the Adobe user forums. All types of users from novices to experts access the user forms and provide tips and advice. If you have a question about Ultra, you're likely to find an answer there.

Run the DirectX Diagnostic Tool

1. Open the DirectX Diagnostic (DxDiag) tool:
 - In Windows XP, choose Start > Run and type `dxdia` in the Open field, and then click OK.
 - In Windows Vista, choose Start and type `dxdia` in the Search text box, and press Enter.

2. When the status bar near the lower-left corner of the dialog box disappears, click the Save All Information button. The Save As dialog box appears.
3. Specify a location and file name, and then click the Save button.
4. Locate and open the resulting file, and copy and paste its contents into your message.

StatusLog.txt file


To troubleshoot some problems, you may also be asked to provide Technical Support with the contents of the StatusLog.txt file. Each time Ultra starts, it makes a list in this file of each component in your system that it attempts to initialize. If startup fails when it reaches a particular component, the cause of the failure may be indicated by the last entry in this file. The problem can sometimes be resolved by updating that component's driver.

The StatusLog.txt file is located here:

Windows XP: C:\Documents and Settings\[*user name*]\Local Settings\Application Data\Adobe\Adobe Ultra CS3

Windows Vista: C:\Users\[*user name*]\AppData\Local\Adobe\Adobe Ultra CS3

Symptoms and solutions

Symptom	Solution
<p>When I click the Set Key button, the subject becomes a ghost, similar to the following image:</p> 	<p>The subject was in the frame when you clicked the Set Key button. To recover, either drag the preview slider to a clear reference frame (with only the color screen background showing) and click the Set Key button again, or use one of the Key Point methods. For more information, see “Setting Key Points (Apply Points Method)” on page 79.</p>
<p>When I play a session in the Output Preview Monitor or save an output movie, the session continues after the input clip ends.</p>	<p>There is a video clip in another layer that either has a longer overall duration than the input clip or has the Offset Into Scene value set so that it continues playing after the input clip ends. Ultra continues playing until it reaches the end of last clip playing.</p> <p>Identify which clips continue playing after the input clip ends, and trim them to end at the same time as the input clip.</p>

Index

Numerics

24-bit 46

32-bit Keyed Source 46

A

action-safe zone 32

active layer

about 24

Adobe Design Center 12

Adobe OnLocation 62

Adobe Video Workshop 11

alpha channel interpretation 65

Apply Points method 79

Aspect menu 64

aspect ratio for virtual sets 65, 103

audio volume 107

B

backdrops 60

backgrounds

about 23

creating 69

bluescreens 60

C

codecs 120

Color Control 37

color screens 60

color settings, saving 110

color, correcting 108

Colors tab 38

correcting color 108

cropping 83, 84

customer support 124

D

defocusing a source 119

Design Center 12

directing for virtual environments 62

DirectX Diagnostic Tool 124

downloads

updates, plug-ins, and tryouts 13

drivers 123

duration 104

DV, Type 1 and Type 2 46

dxdiag 124

F

field order 65

film alpha 65

Flicker Filter 46

flipping input 97

formats, input 67

frame sequences 122

framing 59, 65, 90

full-frame view 33

G

garbage matte 83

GPU Boost 35, 77

graphics cards 77

greenscreens 60

grid controls 34, 99

H

Help 10

I

In point 104
input clips
 about 23
 cropping and masking 83
 playing 28
Input Cropping 44, 84
Input Offset controls 43, 95
Input Preview Monitor 28
Input tab 42
insets
 about 23
 positioning 94
installation 9
introduction 17
Invert Alpha 46, 65

K

key points 79
Keyer settings, saving 88
Keyer tab 35
keying
 Apply Points method 79
 fine tuning 84
 methods 76
 overview 76
 pre-processing background 77
 preserving shadows 82
 removing shadows 81
 Set Key method 78

L

layers
 assigning sources 63
 changing sources 64
 moving and scaling input in 95
 orientation in scene 91
 position in scene 91
 size 91
 thumbnails 28, 29
libraries 47
Live Preview 57

LiveDocs 10
log file 125
looping 105

M

magnifying 33
masking 83, 84
master sets 24
Matte Generation controls 36
menus 48, 51
Move tool 33

N

new session 55
NTSC 9

O

Offset Into Scene 105
Orientation In Scene controls 41
orientation of layers 91
Out point 104
Output Preview Monitor 31
Output tab 45
overlays
 about 23
 creating 70
overview 17, 21

P

PAL 9
Pan & Zoom tab 41
panning 33, 99
Pause Point Settings 40, 107
playing
 input clips 28
 sessions 31
plug-ins 13
 in Adobe Store 13
Plus-90 mode 98
Position In Scene controls 40
position of layers 91
Post-processing controls 38
Pre-processing controls 39
previewing output 31

Q

quick-start 18

R

ReadMe file 10
reflections 44, 111
requirements, system 9
rotating input 97

S

safe area overlay 32
saving
 color settings 88, 110
 output movies 119
 still images 122
scaling input 98
Scene tab 40, 91
sessions
 about 55
 creating 55
 opening 55
 playing and previewing 31
 saving 56
Set Key method 78
Shadows tab 44
shadows, adding 111
shadows, preserving 82
size of layers 91
sliders 34
software downloads 13
sources
 assigning to layers 63
 changing 64
 supported formats 67
 trimming 104
spill, reducing 61
spot masking 83
StatusLog.txt 125
still images, saving 122
support 124
system requirements 9

T

tabs 35
technical support 124

thumbnails, layer 28, 29
timecode fields 34
timing 104
Timing & Settings For Input Clip 42
tools 30
trimming clips 104
troubleshooting 125
tryouts 13
tutorial 18
Type 1 and Type 2 DV 46

U

underscan 58
updates 13, 123
user interface 27

V

video alpha 65
video format, choosing 9
Video Workshop 11
virtual sets
 about 22, 24
 aspect ratio 65
 customizing 73
 default for new session 55
 framing 65
 insets 94
 moving 75
 naming 25
 scaling input 98
VirtualTrak 25, 105
volume, audio 107

W

wardrobe 61
workflow 17

Z

zooming 33, 99

